

# Tutorials & Applications



**HYSYS 3.1**



## Copyright Notice

© 2002 Hyprotech, a subsidiary of Aspen Technology, Inc. All rights reserved.

Hyprotech is the owner of, and have vested in them, the copyright and all other intellectual property rights of a similar nature relating to their software, which includes, but is not limited to, their computer programs, user manuals and all associated documentation, whether in printed or electronic form (the "Software"), which is supplied by us or our subsidiaries to our respective customers. No copying or reproduction of the Software shall be permitted without prior written consent of Aspen Technology, Inc., Ten Canal Park, Cambridge, MA 02141, U.S.A., save to the extent permitted by law.

Hyprotech reserves the right to make changes to this document or its associated computer program without obligation to notify any person or organization. Companies, names, and data used in examples herein are fictitious unless otherwise stated.

Hyprotech does not make any representations regarding the use, or the results of use, of the Software, in terms of correctness or otherwise. The entire risk as to the results and performance of the Software is assumed by the user.

HYSYS, HYSIM, HTFS, DISTIL, HX-NET, and HYPROP III are registered trademarks of Hyprotech.

PIPESYS is a trademark of Neotechnology Consultants.

Microsoft Windows, Windows 95/98, Windows NT, Windows 2000, Visual Basic, and Excel are registered trademarks of the Microsoft Corporation.

## Documentation Credits

Authors of the current release, listed in order of historical start on project (2002-1995):

Pamela Smith; Clement Ng, BSc; Sandy Brar, BSc; Jessie Channey, BAC; Tsitsi Ettienne, BSc; Angeline Teh, BSc; Sarah-Jane Brenner, BSc; Conrad Gierer, BSc; Chris Strashok, BSc; Adeel Jamil, BSc; Yannick Sternon, BIng; Nana Nguyen, BSc; Allan Chau, BSc; Muhammad Sachedina, BSc; Lisa Hugo, BSc, BA; Chris Lowe, PEng; Kevin Hanson, PEng.

Since software is always a work in progress, any version, while representing a milestone, is nevertheless but a point in a continuum. Those individuals whose contributions created the foundation upon which this work is built have not been forgotten. The current authors would like to thank the previous contributors. A special thanks is also extended by the authors to everyone who contributed through countless hours of proof-reading and testing.

## Contacting Hyprotech

Hyprotech can be conveniently accessed via the following:

<b>Web site:</b>	<a href="http://www.hyprotech.com">www.hyprotech.com</a>
<b>Information and Sales:</b>	<a href="mailto:info@hyprotech.com">info@hyprotech.com</a>
<b>Documentation:</b>	<a href="mailto:HypCalgaryDocumentation@hyprotech.com">HypCalgaryDocumentation@hyprotech.com</a>
<b>Training:</b>	<a href="mailto:training@hyprotech.com">training@hyprotech.com</a>
<b>Technical Support:</b>	<a href="mailto:support@hyprotech.com">support@hyprotech.com</a>

Detailed information on accessing Hyprotech Technical Support can be found in the **Technical Support** section of the **Get Started** manual.

TAH3.1-B4814-NOV02-O



# Table of Contents

<b>A</b>	<b>HYSYS Tutorials.....</b>	<b>A-1</b>
<b>1</b>	<b>Gas Processing Tutorial.....</b>	<b>1-1</b>
1.1	Introduction .....	1-3
1.2	Steady State Simulation.....	1-4
1.3	Dynamic Simulation .....	1-98
<b>2</b>	<b>Refining Tutorial.....</b>	<b>2-1</b>
2.1	Introduction .....	2-3
2.2	Steady State Simulation.....	2-5
2.3	Dynamic Simulation .....	2-114
<b>3</b>	<b>Chemicals Tutorial.....</b>	<b>3-1</b>
3.1	Introduction .....	3-3
3.2	Steady State Simulation.....	3-4
3.3	Dynamic Simulation .....	3-76
<b>B</b>	<b>HYSYS Applications.....</b>	<b>B-1</b>
<b>G1</b>	<b>Acid Gas Sweetening with DEA.....</b>	<b>G1-1</b>
G1.1	Process Description .....	G1-3
G1.2	Setup.....	G1-5
G1.3	Steady State Simulation.....	G1-5
G1.4	Simulation Analysis.....	G1-15
G1.5	Calculating Lean & Rich Loadings .....	G1-15
G1.6	Dynamic Simulation .....	G1-17
G1.7	References.....	G1-34



<b>R1</b>	<b>Atmospheric Crude Tower .....</b>	<b>R1-1</b>
R1.1	Process Description .....	R1-3
R1.2	Setup.....	R1-6
R1.3	Steady State Simulation.....	R1-10
R1.4	Results .....	R1-18
<b>R2</b>	<b>Sour Water Stripper.....</b>	<b>R2-1</b>
R2.1	Process Description .....	R2-3
R2.2	Introduction .....	R2-4
R2.3	Setup.....	R2-4
R2.4	Steady State Simulation.....	R2-5
R2.5	Results .....	R2-8
R2.6	Case Study .....	R2-10
<b>P1</b>	<b>Propylene/Propane Splitter .....</b>	<b>P1-1</b>
P1.1	Process Description .....	P1-3
P1.2	Setup.....	P1-4
P1.3	Steady State Simulation.....	P1-5
P1.4	Results .....	P1-10
<b>C1</b>	<b>Ethanol Plant.....</b>	<b>C1-1</b>
C1.1	Process Description .....	C1-3
C1.2	Setup.....	C1-6
C1.3	Steady State Simulation.....	C1-6
C1.4	Results .....	C1-13
<b>C2</b>	<b>Synthesis Gas Production.....</b>	<b>C2-1</b>
C2.1	Process Description .....	C2-3
C2.2	Setup.....	C2-4
C2.3	Steady State Simulation.....	C2-9
C2.4	Results .....	C2-16
<b>X1</b>	<b>Case Linking.....</b>	<b>X1-1</b>
X1.1	Process Description .....	X1-3
X1.2	Building Flowsheet 1 .....	X1-4
X1.3	Building Flowsheet 2 .....	X1-8
X1.4	Creating a User Unit Operation.....	X1-10



# A HYSYS Tutorials

The Tutorials section of this manual presents you with independent tutorial sessions. Each tutorial guides you step-by-step through the complete construction of a HYSYS simulation. The tutorial(s) you choose to work through will likely depend on the simulation topic that is most closely related to your work, your familiarity with HYSYS and the types of simulation cases you anticipate on creating in the future.

All completed Tutorial cases are included with your HYSYS package, and are available on **HYSYS\Samples**.

Regardless of which tutorial you work through first, you will gain the same basic understanding of the steps and tools used to build a HYSYS simulation. After building one of these tutorial cases, you might choose to build one or several more, or begin creating your own simulations.

**If you are new to HYSYS, it is recommended that you begin with the steady state tutorials. These tutorials explicitly detail each step required to complete the simulation. In steps where more than one method is available to complete a particular action, all methods are outlined. The dynamic tutorials (which are continued after the steady state section) are also presented in a step-by-step manner, but are less detailed in their explanations. They assume a rudimentary knowledge of the HYSYS interface and methods.**

The three tutorials are grouped in three general areas of interest:

1. Gas Processing
2. Refining
3. Chemicals

Each area has an associated steady state and dynamic tutorial. The dynamic tutorials use the steady state cases and add control schemes and dynamic specifications required to run the case in Dynamic mode. If you are interested only in steady state simulation, go through the steady state tutorial(s) that most interest you and stop at the dynamics section. If you are interested only in learning to apply dynamic simulation methods, use the pre-built steady state base case, included with HYSYS, as the starting point for your dynamic tutorial case.



## Introduction

There are also several HYSYS training courses available. Contact your Hyprotech agent for more information, or visit the training page of our web site [www.hyprotech.com](http://www.hyprotech.com).

The solved steady state cases are saved in the **HYSYS\Samples** folder as TUTOR1.hsc, TUTOR2.hsc, and TUTOR3.hsc files.

For the dynamics tutorials, you can use the pre-built steady state cases as your starting point. The solved dynamics cases are also included as dyntut1.hsc, dyntut2.hsc, and dyntut3.hsc.

In the chapters that follow, example problems are used to illustrate some of the basic concepts of building a simulation in HYSYS. Three complete tutorials are presented:

1. Gas Processing
  - **Steady State.** Models a sweet gas refrigeration plant consisting of an inlet separator, gas/gas heat exchanger, chiller, low-temperature separator and de-propanizer column.
  - **Dynamics.** Models the Gas Processing tutorial case in Dynamic mode. This tutorial makes use of the recommendations of the Dynamic Assistant when building the case.
2. Refining
  - **Steady State.** Models a crude oil processing facility consisting of a pre-flash drum, crude furnace and an atmospheric crude column.
  - **Dynamics.** Models the Refining example problem in Dynamic mode.
3. Chemicals
  - **Steady State.** Models a propylene glycol production process consisting of a continuously-stirred-tank reactor and a distillation tower.
  - **Dynamics.** Models the Chemicals example problem in Dynamic mode. This tutorial make use of the recommendations of the Dynamic Assistant when building the case.

Each of these tutorials will guide you step-by-step through the complete construction of a HYSYS simulation. The tutorial you choose first will likely depend on which one is most closely related to your work, or that you feel most comfortable with.

Regardless of the tutorial you work through first, you will gain the same basic understanding of the steps and tools used to build a HYSYS simulation. Each example contains detailed instructions for choosing a property package and components, installing and defining streams, unit operations and columns, and using various aspects of the HYSYS interface to examine the results while you are creating the simulation. If you are new to HYSYS, it is recommended that you begin with one of these tutorials in order to familiarize yourself with the initial steps required to build a HYSYS simulation.

Often in HYSYS, more than one method exists for performing a task or executing a command. Many times you can use the keyboard, the



mouse, or a combination of both to achieve the same result. The steady state tutorials attempt to illustrate HYSYS' flexibility by showing you as many of these alternative methods as possible. You can then choose which approach is most appropriate for you.

The dynamics tutorials use the steady state solution as a basis for building the dynamic case. If you like, you can build the steady state case and then proceed with the dynamic solution, or you can simply call up the steady state case from disk and begin the dynamic modeling.

## Starting HYSYS




HYSYS Icon

With Windows NT 4.0 or Windows 95/98, the installation process creates a shortcut to HYSYS:

1. Click on the **Start** menu.
2. Move from **Programs** to **Hyprotech** to **HYSYS**.
3. Select **HYSYS**.

The HYSYS Desktop appears:



To learn more about the basics of the HYSYS interface, see [Chapter 1 - Interface](#) in the **User Guide**.



## Get Started

The tutorials start in Steady State mode, and end in Dynamic mode.

Once you have completed one or more tutorials, you may want to examine the Applications section for other examples that may be of interest.

You are now ready to begin building a HYSYS simulation, so proceed to the Tutorial of your choice.

<b>Tutorial</b>	<b>Chapter</b>	<b>Samples Case Name (Steady State/Dynamic)</b>
<b>Gas Processing</b>	Chapter 1	TUTOR1.HSC dyntut1.hsc
<b>Refining</b>	Chapter 2	TUTOR2.HSC dyntut2.hsc
<b>Chemicals</b>	Chapter 3	TUTOR3.HSC dyntut3.hsc



# 1 Gas Processing Tutorial

<b>1.1 Introduction .....</b>	<b>3</b>
<b>1.2 Steady State Simulation .....</b>	<b>4</b>
1.2.1 Process Description .....	4
1.2.2 Setting Your Session Preferences .....	6
1.2.3 Building the Simulation .....	10
1.2.4 Entering the Simulation Environment .....	18
1.2.5 Using the Workbook .....	20
1.2.6 Installing Unit Operations .....	34
1.2.7 Using Workbook Features .....	45
1.2.8 Using the PFD .....	49
1.2.9 Viewing and Analyzing Results .....	76
1.2.10 Optional Study .....	87
<b>1.3 Dynamic Simulation .....</b>	<b>98</b>
1.3.1 Modifying the Steady State Flowsheet .....	99
1.3.2 Column Sizing .....	107
1.3.3 Using the Dynamics Assistant .....	113
1.3.4 Adding Controller Operations .....	119







# 1.1 Introduction


The simulation will be built using these basic steps:

1. Create a unit set.
2. Choose a property package.
3. Select the components.
4. Create and specify the feed streams.
5. Install and define the unit operations prior to the column.
6. Install and define the column.

A solved case is located in the file **TUTOR1.HSC** in your **HYSYS\Samples** directory.

In this Tutorial, a natural gas stream containing **N<sub>2</sub>**, **CO<sub>2</sub>**, and **C<sub>1</sub> through nC<sub>4</sub>** is processed in a refrigeration system to remove the heavier hydrocarbons. The lean, dry gas produced will meet a pipeline hydrocarbon dew point specification. The liquids removed from the rich gas are processed in a depropanizer column, yielding a liquid product with a specified propane content. A flowsheet for this process is shown below.

Figure 1.1



The following pages will guide you through building a HYSYS case to illustrate the complete construction of the simulation, from selecting a property package and components to examining the final results. The tools available in HYSYS interface will be utilized to illustrate the flexibility available to you.

**Before proceeding, you should have read the introductory chapter which precedes the Tutorials in this manual.**




## 1.2 Steady State Simulation

### 1.2.1 Process Description

This tutorial will model a natural gas processing facility that uses propane refrigeration to condense liquids from the feed and a distillation tower to process the liquids. The flowsheet for this process appears below.

Figure 1.2



The combined feed stream enters an inlet separator, which removes the free liquids. Overhead gas from the Separator is fed to the gas/gas exchanger, where it is pre-cooled by already refrigerated gas. The cooled gas is then fed to the chiller, where further cooling is accomplished through exchange with evaporating propane (represented by the C3Duty stream). In the chiller, which will be modeled simply as a Cooler, enough heavier hydrocarbons condense such that the eventual sales gas meets a pipeline dew point specification. The cold stream is then separated in a low-temperature separator (LTS). The dry, cold gas is fed to the gas/gas exchanger and then to sales, while the condensed liquids are mixed with free liquids from the inlet separator. These liquids are processed in a depropanizer column to produce a low-propane-content bottoms product.



Once the results for the simulation have been obtained, you will have a good understanding of the basic tools used to build a HYSYS simulation case. At that point, you can either proceed with the Optional Study presented at the end of the tutorial or begin building your own simulations.

In this tutorial, three logical operations will be installed in order to perform certain functions that cannot be handled by standard physical unit operations:

Logical	Flowsheet Function
<b>Balance</b>	To duplicate the composition of the SalesGas stream in order to calculate its dew point temperature at pipeline specification pressure.
<b>Adjust</b>	To determine the required LTS temperature which gives a specified SalesGas dew point.
<b>HYSYS Spreadsheet</b>	To calculate the SalesGas net heating value.

The Balance operation will be installed in the main example. In the Optional Study section, the Adjust and Spreadsheet operations will be installed to investigate the effect of the LTS temperature on the sales gas heating value.

The two primary building tools, the Workbook and the PFD, will be used to install the streams and operations and to examine the results while progressing through the simulation. Both of these tools provide you with a lot of flexibility in building your simulation and in quickly accessing the information you need.

The Workbook will be used to build the first part of the flowsheet, starting with the feed streams and building up to and including the gas/gas heat exchanger. The PFD will be used to install the remaining operations, from the chiller through to the column.



## 1.2.2 Setting Your Session Preferences

All commands accessed via the toolbar are also available as menu items.




New Case icon

The Simulation Basis Manager allows you to create, modify, and manipulate fluid packages in your simulation case. Most of the time, as with this example, you will require only one fluid package for your entire simulation.

1. To start a new simulation case, do one of the following:
  - From the **File** menu, select **New Case**.
  - Click the **New Case** icon.

The Simulation Basis Manager appears:

Figure 1.3




Next, you will set your Session Preferences before building a case.



- From the **Tools** menu, select **Preferences**. The Session Preferences view appears.  
You should be on the **Options** page of the **Simulation** tab.

Figure 1.4



- In the General Options group, ensure the **Use Modal Property Views** checkbox is **unchecked**.

## Creating a New Unit Set

The first step in building the simulation case is choosing a unit set. Since HYSYS does not allow you to change any of the three default unit sets listed, you will create a new unit set by cloning an existing one. For this example, a new unit set will be made based on the HYSYS **Field** set, which you will then customize.

To create a new unit set, do the following:


- In the Session Preferences view, click the **Variables** tab.
- Select the **Units** page if it is not already selected.



The default Preference file is named **HYSYS.prp**. When you modify any of the preferences, you can save the changes in a new Preference file by clicking the **Save Preference Set** button. HYSYS prompts you to provide a name for the new Preference file, which you can load into any simulation case by clicking the **Load Preference Set** button.

3. In the Available Unit Sets group, select **Field** to make it the active set.

**Figure 1.5**




4. Click the **Clone** button. A new unit set named **NewUser** appears. This unit set becomes the currently Available Unit Set.
5. In the **Unit Set Name** field, enter a name for the new unit set. You can now change the units for any variable associated with this new unit set.

In the Display Units group, the current default unit for Flow is lbmole/hr. A more appropriate unit for this example is **MMSCFD**.




- To view the available units for Flow, click the drop-down arrow in the Flow cell.

Figure 1.6



- Scroll through the list using either the scroll bar or the arrow keys, select MMSCFD, then press ENTER.

Figure 1.7



Your new unit set is now defined.

- Click the **Close** icon (in the top right corner) to close the Session Preferences view. You will now start building the simulation.



Close icon



## 1.2.3 Building the Simulation


### Creating a Fluid Package

The next step is to create a Fluid Package. As a minimum, a Fluid Package contains the components and property method (for example, an Equation of State) HYSYS will use in its calculations for a particular flowsheet. Depending on what is required in a specific flowsheet, a Fluid Package may also contain other information such as reactions and interaction parameters.

1. On the Simulation Basis Manager view, click the **Fluid Pkgs** tab.
2. Click the **Add** button, and the property view for your new Fluid Package appears.

HYSYS has created a Fluid Package with the default name **Basis-1**. You can change the name of this fluid package by typing a new name in the **Name** field at the bottom of the view.

Figure 1.8



The property view is divided into a number of tabs to allow you to supply all the information necessary to completely define the Fluid Package. For this example, the Set Up tab and Component List Selection group will be used.

You choose the Property Package on the **Set Up** tab. The currently selected Property Package is <none>. There are a number of ways to select a property package.


For this tutorial, you will select the Peng Robinson property package.



3. Do **one** of the following:


- Start typing **PENG ROBINSON**, and HYSYS will find the match to your input.
- Use the up and down keys to scroll through the list of available property packages until **Peng Robinson** is selected.
- Use the vertical scroll bar to move down the list until **Peng Robinson** becomes visible, then select it.

**Figure 1.9**




The Property Pkg indicator at the bottom of the view now indicates that Peng Robinson is the current property package for this Fluid Package.

**Figure 1.10**



Alternatively, you could have selected the EOSs radio button in the Property Package Filter group, which would produce a list of only those property packages which are Equations of State. You could have then selected Peng Robinson from this filtered list, as shown in the following figure.

**Figure 1.11**






## Selecting Components

Now that you have chosen the property package to be used in the simulation, the next step is to select the components.

1. On the Component List Selection drop-down list, select Component List-1, if it is not already selected.
2. Click the **View** button. The Component List View appears.

Figure 1.12



There are a number of ways to select components for your simulation. One method is to use the matching feature. Each component is listed in three ways on the Selected tab:

Matching Method	Description
<b>SimName</b>	The name appearing within the simulation.
<b>FullName/Synonym</b>	IUPAC name (or similar), and synonyms for many components.
<b>Formula</b>	The chemical formula of the component. This is useful when you are unsure of the library name of a component, but know its formula.

At the top of each of these three columns is a corresponding radio button. Based on the selected radio button, HYSYS will locate the component(s) that best matches the input you type in the Match cell.




For this tutorial, you will add the following components: N2, CO2, C1, C2, C3, iC4 and nC4.

First, you will add nitrogen using the match feature.

3. Ensure the **FullName/Synonym** radio button is selected, and the **Show Synonyms** checkbox is checked.
4. Move to the **Match** field by clicking on the field, or by pressing **ALT M**.
5. Type **NITROGEN**. HYSYS will filter as you type, displaying only those components that match your input.

Figure 1.13



6. With **Nitrogen** selected, add it to the Current Composition List by doing **one** of the following:
  - Press the **ENTER** key.
  - Click the **Add Pure** button.
  - Double-click on **Nitrogen** (note that Nitrogen need not be highlighted for this option).

In addition to the Match criteria radio buttons, you can also use the Filters view to display only those components belonging to certain families.


Next you will add CO2 to the component list using the filter feature.

7. Ensure the Match cell is empty by pressing **ALT M** and **DELETE**.



8. Click the **View Filters** button. The Filters view appears as shown in the following.

Figure 1.14



9. Check the **Use Filter** checkbox.
10. CO<sub>2</sub> does not fit into any of the standard families, so check the **Miscellaneous** checkbox.
11. Scroll down the filtered list until CO<sub>2</sub> becomes visible.
12. Double-click the **CO<sub>2</sub>** component to add it to the component list. The Match feature remains active when you use a filter, so you could also type CO<sub>2</sub> in the Match cell, select it, then add it to the component list.

To select consecutive components, use the **SHIFT** key. To select non-consecutive components, use the **CTRL** key.

To add the remaining components **C1** through **nC4** using the filter, uncheck the **Miscellaneous** checkbox, and check the **Hydrocarbons** box.




The following shows you a quick way to add components that appear consecutively in the library list:

1. Click on the first component in the list (in this case, **C1**).
2. Do **one** of the following:
  - Hold the **SHIFT** key and click on the last component required, in this case **nC4**. All components **C1** through **nC4** will now be selected. Release the **SHIFT** key.
  - Click and hold on **C1**, drag down to **nC4**, and release the mouse button. **C1** through **nC4** will be selected.
3. Click the **Add Pure** button. The highlighted components are transferred to the **Selected Components** list.

The completed component list appears below.

**Figure 1.15**



A component can be removed from the Current Components List by selecting it, and clicking the **Remove** button or the **DELETE** key.

## Viewing Component Properties


To view the properties of one or more components, select the component(s) and click the **View Component** button. HYSYS opens the property view(s) for the component(s) you selected. For example:

1. Click on **CO2** in the Selected Components list.
2. Press and hold the **CTRL** key.
3. Click on **n-Butane**. The two components should now be selected.




4. Release the CTRL key.

Figure 1.16



5. Click the **View Component** button. The property views for the two components appear.

Figure 1.17





See [Chapter 3 - Hypotheticals](#) in the Simulation Basis manual for more information about cloning library components.


If the Simulation Basis Manager is not visible, select the **Home View** icon from the toolbar.



The Component property view only allows you to view the pure component information. You cannot modify any parameters for a library component, however, HYSYS allows you to clone a library component as a Hypothetical component, which you can then modify as required.

Close both of the component views and the Component List View to return to the Fluid Package. If your project required it, you could continue to add information such as interaction parameters and reactions to the Fluid Package. For the purposes of this tutorial, however, the Fluid Package is now completely defined. Close the Fluid Package view to return to the Simulation Basis Manager.

Figure 1.18



The list of Current Fluid Packages now displays the new Fluid Package, Basis-1, and shows the number of components (NC) and property package (PP). The new Fluid Package is assigned by default to the main flowsheet, as shown in the Flowsheet-Fluid Pkg Associations group. Now that the Basis is defined, you can install streams and operations in the Main Simulation environment.

To leave the Basis environment and enter the Simulation environment, do one of the following:

- Click the **Enter Simulation Environment** button on the Simulation Basis Manager view.
- Click the **Enter Simulation Environment** icon on the tool bar.



Enter Simulation Environment icon




## 1.2.4 Entering the Simulation Environment

When you enter the Simulation environment, the initial view that appears depends on your current Session Preferences setting for the Initial Build Home View. Three initial views are available:

1. PFD
2. Workbook
3. Summary

Any or all of these can be displayed at any time; however, when you first enter the Simulation environment, only one appears. In this example, the initial Home View is the PFD (HYSYS default setting).

**Figure 1.19**





There are several things to note about the Main Simulation environment. In the upper right corner, the Environment has changed from Basis to Case (Main). A number of new items are now available in the menu bar and tool bar, and the PFD and Object Palette are open on the Desktop. These latter two objects are described below.

You can toggle the palette open or closed by pressing **F4**, or by selecting the Open/Close Object Palette command from the Flowsheet menu.

Objects	Description
<b>PFD</b>	The PFD is a graphical representation of the flowsheet topology for a simulation case. The PFD view shows operations and streams and the connections between the objects. You can also attach information tables or annotations to the PFD. By default, the view has a single tab. If required, you can add additional PFD pages to the view to focus in on the different areas of interest.
<b>Object Palette</b>	A floating palette of buttons that can be used to add streams and unit operations.

Before proceeding any further, save your case.

Do **one** of the following:


- Click the **Save** icon on the toolbar.
- From the **File** menu, select **Save**.
- Press **CTRL S**.



Save icon


If this is the first time you have saved your case, the Save Simulation Case As view appears.

Figure 1.20





When you choose to open an existing case by clicking the

**Open Case** icon , or by selecting **Open Case** from the File menu, a view similar to the one shown in [Figure 1.20](#) appears. The File Filter drop-down list will then allow you to retrieve backup (\*.bk\*) and HYSIM (\*.sim) files in addition to standard HYSYS (\*.hsc) files.

By default, the File Path is the Cases sub-directory in your HYSYS directory. To save your case, do the following:

1. In the **File Name** cell, type a name for the case, for example **GASPLANT**. You do not have to enter the .hsc extension; HYSYS will automatically add it for you.
2. Once you have entered a file name, press the ENTER key or click the **Save** button. HYSYS will now save the case under the name you have given it when you save in the future. The Save As view will not appear again unless you choose to give it a new name using the **Save As** command. If you enter a name that already exists in the current directory, HYSYS will ask you for confirmation before over-writing the existing file.

## 1.2.5 Using the Workbook



Workbook icon

The Workbook displays information about streams and unit operations in a tabular format, while the PFD is a graphical representation of the flowsheet. Click the Workbook icon on the toolbar to ensure the Workbook window is active.

## Installing the Feed Streams

In general, the first action you perform when you enter the Simulation environment is installing one or more feed streams. The following procedure explains how to create a new stream.


1. On the **Material Streams** tab of the Workbook, type the stream name **Feed 1** in the cell labelled **\*\*New\*\***.

HYSYS accepts blank spaces within a stream or operation name.



2. Press ENTER. HYSYS will automatically create the new stream with the name defined in step #1. Your Workbook should appear as shown below.

Figure 1.21



Next you will define the feed conditions.

When you pressed ENTER after typing in the stream name, HYSYS automatically advanced the active cell down one to Vapour Fraction.

1. Move to the **Temperature** cell for Feed 1 by clicking it, or by pressing the Down arrow key.
2. Type 60 in the **Temperature** cell.  
In the Unit drop-down list, HYSYS displays the default units for temperature, in this case F. This is the correct unit for this exercise.
3. Press the ENTER key.

Your active location should now be the Pressure cell for Feed 1. If you know the stream pressure in another unit besides the default unit of psia, HYSYS will accept your input in any one of a number of different units and automatically convert the supplied value to the default for you. For this example, the pressure of Feed 1 is 41.37 bar.





1. In the **Pressure** cell, type 41.37.
2. Click the  in the Unit drop-down list to open the list of units, or press the SPACE BAR to move to the Units drop-down list.

Figure 1.22



3. Either scroll through the list to find **bar**, or begin typing it. HYSYS will match your input to locate the required unit.
4. Once **bar** is selected, press the ENTER key. HYSYS will automatically convert the pressure to the default unit, **psia**.

When you press ENTER, the active selection moves to the Molar Flow cell for Feed 1.

5. In the **Molar Flow** cell, type 6 and press ENTER. The default Molar Flow unit is already MMSCFD, so you do not have to modify the units.



## Providing Compositional Input

In the previous section you specified the stream conditions. Next you will input the composition information.



1. Close the Workbook view.  
The PFD becomes visible and displays a light blue arrow on it, labeled Feed 1. That arrow is the stream Feed 1 that you just created.
2. Double-click the blue arrow.  
The Feed 1 view appears.

Figure 1.23

Feed 1	
Stream Name	Feed 1
Vapour / Phase Fraction	<empty>
Temperature [F]	60.000
Pressure [psia]	600.02
Molar Flow [MMSCFD]	6.0000
Mass Flow [lb/hr]	<empty>
Std Ideal Liq Vol Flow [barrel/day]	<empty>
Molar Enthalpy [Btu/lbmole]	<empty>
Molar Entropy [Btu/lbmole-F]	<empty>
Heat Flow [Btu/hr]	<empty>
Liq Vol Flow @Std Cond [barrel/day]	<empty>
Fluid Package	Basis-1

Worksheet Attachments Dynamics


Unknown Compositions

Delete Define from Other Stream...




- Click on the **Composition** page. By default, the components are listed by Mole Fractions.

Figure 1.24



- Click on the **Mole Fractions** cell for the first component, **Nitrogen**.
- Type 0.01 and press ENTER. HYSYS will display the Input Composition for Stream view, where you will complete the compositional input.

Figure 1.25





This view allows you to access certain features designed to streamline the specification of a stream composition. The following table lists and describes the features available on this view:

Composition Input	Feature Description
<b>Composition Basis Radio Buttons</b>	Allows you to input the stream composition in some fractional basis other than Mole Fraction, or by component flows, by selecting the appropriate radio button before providing your input.
<b>Normalizing</b>	<p>The Normalizing feature allows you to enter the relative ratios of components; for example, 2 parts N<sub>2</sub>, 2 parts CO<sub>2</sub>, 120 parts C<sub>1</sub>, etc. Rather than manually converting these ratios to fractions summing to one, enter the individual numbers of parts and click the Normalize button. HYSYS will compute the individual fractions to total 1.0.</p> <p>Normalizing is also useful when you have a stream consisting of only a few components. Instead of specifying zero fractions (or flows) for the other components, enter the fractions (or the actual flows) for the non-zero components, leaving the others &lt;empty&gt;. Click the Normalize button, and HYSYS will force the other component fractions to zero.</p>
<b>Calculation status/ colour</b>	<p>As you input the composition, the component fractions (or flows) initially appear in red, indicating the final composition is unknown. These values will become blue when the composition has been calculated. Three scenarios will result in the stream composition being calculated:</p> <ul style="list-style-type: none"> <li>• Input the fractions of all components, including any zero components, such that their total is exactly 1.0000. Then click the OK button.</li> <li>• Input the fractions (totalling 1.000), flows or relative number of parts of all non-zero components. Click the Normalize button, then the OK button.</li> <li>• Input the flows or relative number of parts of all components, including any zero components, then click the OK button.</li> </ul>

These are the default colours; yours may appear different depending on your settings on the Colours page of the Session Preferences view.



1. Click on the Mole Fraction cell for CO<sub>2</sub>, type 0.01, then press ENTER.
2. Enter the remaining fractions as shown in the figure below. When you have entered the fraction of each component the total at the bottom of the view will equal 1.00000.

Figure 1.26

	MoleFraction
Nitrogen	0.0100
CO2	0.0100
Methane	0.6000
Ethane	0.2000
Propane	0.1000
i-Butane	0.0400
n-Butane	0.0400
Total	1.0000

Composition Basis:

- ☒ Mole Fractions
- ☐ Mass Fractions
- ☐ Liq Volume Fractions
- ☐ Mole Flows
- ☐ Mass Flows
- ☐ Liq Volume Flows

Composition Controls:

Erase

Normalize

Cancel

OK

3. Click the OK button, and HYSYS accepts the composition. The stream is now completely defined, so HYSYS flashes it at the conditions given to determine its remaining properties.

Figure 1.27

	Mole Fractions
Nitrogen	0.010000
CO2	0.010000
Methane	0.600000
Ethane	0.200000
Propane	0.100000
i-Butane	0.040000
n-Butane	0.040000
Total	1.00000

Worksheet

Conditions

Properties

Composition

K Value

User Variables

Notes

Cost Parameters

Edit...

Edit Properties...

Basjs...

Worksheet Attachments Dynamics

OK

Delete Define from Other Stream...

If you want to delete a stream, click on it in the PFD, then press the **DELETE** key. HYSYS will ask for confirmation before deleting.

You can also delete the stream using the Delete button on that stream's view.

4. Close this view, then return to the Workbook by clicking on the Workbook button.



5. Ensure that the **Material Streams** tab is active. The properties of Feed 1 appear below. The values you specified are a different colour (blue) than the calculated values (black).

Figure 1.28

Name	Feed 1	New
Vapour Fraction	0.8952	
Temperature [F]	60.00	
Pressure [psia]	600.0	
Molar Flow [MMSCFD]	6.000	
Mass Flow [lb/hr]	1.675e+004	
Liquid Volume Flow [barrel/day]	3012	
Heat Flow [Btu/hr]	-2.553e+007	

Material Streams   Compositions   Energy Streams   Unit Ops


ProductBlock\_Feed 1  
FeederBlock\_Feed 1

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0

## Alternative Methods for Defining Streams

In addition to the method you just learned, there are several alternative ways to define streams via the Workbook.

1. The Object Palette should be visible; if not, press F4.
2. To add another feed stream, do any **one** of the following:
  - Press F11.
  - From the Flowsheet menu, select **Add Stream**.
  - Double-click the **Material Stream** icon on the Object Palette.
  - Click the **Material Stream** icon on the Object Palette, then click on the **Add Object** icon.



Each of these four methods displays the property view for the new stream, which will be named according to the Automatic Naming of Flowsheet Objects setting defined in the Session Preferences (Simulation tab, Naming page). HYSYS will name new material streams with numbers starting at 1 and new energy streams starting at Q-100.

When you initially access the stream property view, the Conditions page on the Worksheet tab is the active page, and 1 appears in the Stream Name cell.



Next you will define this second feed stream:

3. In the **Stream Name** cell, replace the name by typing **Feed 2**, then press ENTER.
4. Enter the following values:
  - Temperature: 60
  - Pressure: 600
  - Molar Flow: 4

All these variables are in the default units.

Figure 1.29

Worksheet	Stream Name	Feed 2
Conditions	Vapour / Phase Fraction	<empty>
Properties	Temperature [F]	60.000
	Pressure [psia]	600.00
Composition	Molar Flow [MMSCFD]	4.0000
K Value	Mass Flow [lb/hr]	<empty>
User Variables	Std Ideal Liq Vol Flow [barrel/day]	<empty>
Notes	Molar Enthalpy [Btu/lbmole]	<empty>
Cost Parameters	Molar Entropy [Btu/lbmole-F]	<empty>
	Heat Flow [Btu/hr]	<empty>
	Liq Vol Flow @Std Cond [barrel/day]	<empty>
	Fluid Package	Basis-1

Worksheet Attachments Dynamics

Unknown Compositions

Delete Define from Other Stream...

5. Click the **Composition** page.

Figure 1.30

Worksheet	Mole Fractions
Conditions	Nitrogen
Properties	CO2
Composition	Methane
K Value	Ethane
User Variables	Propane
Notes	i-Butane
Cost Parameters	n-Butane

Total 0.00000

Edit... Edit Properties... Basis...

Worksheet Attachments Dynamics

Unknown Compositions

Delete Define from Other Stream...



- Click the **Edit** button at the bottom of the Composition page. The Input Composition for Stream view appears.

**Figure 1.31**

The screenshot displays the "Input Composition for Stream: Feed 2" window. It features a table for defining the stream's composition. The components listed are Nitrogen, CO<sub>2</sub>, Methane, Ethane, Propane, i-Butane, and n-Butane, followed by five blank rows. Each component has a corresponding entry in the "MoleFraction" column, all currently set to "<empty>". Below the table, the "Total" field is shown with a value of "0.0000". To the right of the table, the "Composition Basis" section allows selection between different units: Mole Fractions (which is selected), Mass Fractions, Liq Volume Fractions, Mole Flows, Mass Flows, and Liq Volume Flows. The "Composition Controls" section includes four buttons: "Erase", "Normalize", "Cancel", and "OK".

- 
- Figure 1.32**
- |                 | MassFraction |
|-----------------|--------------|
| Nitrogen        | 6.0000       |
| CO <sub>2</sub> | 0.0000       |
| Methane         | 1.2000e+02   |
| Ethane          | 6.0000e+01   |
| Propane         | 6.0000e+01   |
| i-Butane        | 3.0000e+01   |
| n-Butane        | 2.4000e+01   |
|                 |              |
|                 |              |
|                 |              |
|                 |              |
|                 |              |
|                 |              |
| Total           | 3.0000e+02   |
- Composition Basis:**
- ☐ Mole Fractions
  - ☒ Mass Fractions
  - ☐ Liq Volume Fractions
  - ☐ Mole Flows
  - ☐ Mass Flows
  - ☐ Lig Volume Flows
- Composition Controls:**
- Erase
- Normalize
- Cancel
- OK



11. Click the **Normalize** button once you have entered the parts, and HYSYS will convert your input to component mass fractions.

**For CO2 (the component you left <empty>), the Mass Fraction was automatically forced to zero.**


**Figure 1.33**

	MassFraction
Nitrogen	0.0200
CO2	0.0000
Methane	0.4000
Ethane	0.2000
Propane	0.2000
i-Butane	0.1000
n-Butane	0.0800
Total	1.0000

12. Click the **OK** button to close the view and return to the stream property view.

HYSYS has performed a flash calculation to determine the unknown properties of Feed 2, as shown by the status indicator displaying OK.

**Figure 1.34**




To view the properties of each phase, use the horizontal scroll bar in the table on the property view, or drag and expand the window to view all property columns.





Sizing Arrow Cursor



To expand the property view, move your cursor over the right border of the view. The cursor becomes a sizing arrow. With the arrow visible, click and drag to the right until the horizontal scroll bar disappears, leaving the entire table visible.

The compositions currently appear in Mass Fraction. To change this, click the Basis button, then select another Compositional Basis radio button in the view that appears.

To view the calculated stream properties, click the Conditions page. New or updated information is automatically and instantly transferred among all locations in HYSYS.

Figure 1.35

Feed 2

Worksheet

Conditions

Properties

Composition

K Value

User Variables

Notes

Cost Parameters

Stream Name	Feed 2	Vapour Phase	Liquid Phase
Vapour / Phase Fraction	0.90127	0.90127	0.09873
Temperature [F]	60.000	60.000	60.000
Pressure [psia]	600.00	600.00	600.00
Molar Flow [MMSCFD]	4.0000	3.6051	0.39492
Mass Flow [lb/hr]	11000	9230.7	1768.9
Std Ideal Liq Vol Flow [barrel/day]	1983.1	1731.0	252.06
Molar Enthalpy [Btu/lbmole]	-3.706e+004	-3.553e+004	-5.096e+004
Molar Entropy [Btu/lbmole-F]	35.552	36.628	25.726
Heat Flow [Btu/hr]	-1.6276e+07	-1.4066e+07	-2.2096e+06
Liq Vol Flow @Std Cond [barrel/day]	<empty>	<empty>	258.76
Fluid Package	Basis-1		

Worksheet

Attachments

Dynamics

OK

Delete

Define from Other Stream...

## Viewing a Phase Diagram


You can view a phase diagram for any material stream using the HYSYS Envelope Utility.

1. On the property view for stream Feed 2, click the **Attachments** tab, then select the **Utilities** page.
2. To create a phase envelope for the stream, click the **Create** button. The Available Utilities view appears, displaying a list of HYSYS utilities.



3. Do **one** of the following:
  - Select **Envelope**, and click the **Add Utility** button.
  - Double-click on **Envelope**.

Figure 1.36




The Envelope Utility view appears. HYSYS creates and displays a phase envelope for the stream. Just as with a Stream, a Utility has its own property view containing all the information needed to define the utility. Initially, the Connections page of the Design tab appears.

To make the envelope property view more readable, maximize or re-size the view.

4. Click the **Performance** tab, then select the **Plots** page.  
The default Envelope Type is PT.
5. To view another envelope type, select the appropriate radio button in the Envelope type group. Depending on the type of envelope selected, you can specify and display Quality curves, Hydrate curves, Isotherms, and Isobars. To view the data in a tabular format, select the **Table** page.

Figure 1.37






6. Click the **Design** tab. The Design tab allows you to change the name of the Utility and the stream that it is attached to, and view Critical Values and Maxima.

A Utility is a separate entity from the stream to which it is attached; if you delete it, the stream will not be affected.

Likewise, if you delete the stream, the Utility will remain but will not display any information until you attach another stream using the Select Stream button.

Figure 1.38



7. Close this Utility view since it is no longer required. For more information about defining utilities, refer to [Section 7.27 - Utilities](#) in the **User Guide**.
8. Close the Feed 2 view.



## 1.2.6 Installing Unit Operations

In the last section you defined the feed streams. Now you will install the necessary unit operations for processing the gas.

### Installing the Mixer


The first operation that you will install is a Mixer, used to combine the two feed streams. As with most commands in HYSYS, installing an operation can be accomplished in a number of ways. One method is through the Unit Ops tab of the Workbook.



Workbook icon

1. Click the **Workbook** icon to ensure the Workbook window is active.
2. Click the **Unit Ops** tab of the Workbook.

Figure 1.39






- Click the **Add UnitOp** button. The UnitOps view appears, listing all available unit operations.

When you click the **Add** button or press the **ENTER** key inside this view, HYSYS adds the operation that is currently selected.

You can also double-click an operation to install it.

**Figure 1.40**




- Select **Mixer** by doing one of the following:
  - Start typing 'mixer'.
  - Press the Down arrow key to scroll down the list of available operations to Mixer.
  - Scroll down the list using the vertical scroll bar and click on **Mixer**.
- With Mixer selected, click the **Add** button, or press the **ENTER** key.

You can also use the filters to find and add an operation.

- For the Mixer operation, select the **Piping Equipment** radio button under Categories. A filtered list appears in the Available Unit Operations group.
- Double-click the **Mixer** operation to install it. The Mixer property view appears.

**Figure 1.41**





See [Section 12.2.3 - Naming Page](#) in the User Guide for detailed information on setting your Session Preferences.


As with a stream, a unit operation's property view contains all the information defining the operation, organized in tabs and pages. The four tabs shown for the Mixer, namely Design, Rating, Worksheet and Dynamics, appear in the property view for most operations. More complex operations have more tabs. HYSYS provides the default name MIX-100 for the Mixer. As with streams, the default naming scheme for unit operations can be changed on the Session Preferences view.

Many operations, such as the Mixer, accept multiple feed streams. Whenever you see a table like the one in the Inlets group, the operation will accept multiple stream connections at that location. When the Inlets table has focus, you can access a drop-down list of available streams.

Now you will complete the Connections page:

6. Click the <<Stream>> cell to ensure the Inlets table is active. The status bar at the bottom of the view shows that the operation requires a feed stream.
7. Open the <<Stream>> drop-down list of feeds by clicking on ▼ or by pressing the F2 key and then the Down arrow key.

Figure 1.42



Alternatively, you can make the connections by typing the exact stream name in the cell, then pressing ENTER.

8. Select **Feed 1** from the list. The stream is transferred to the list of Inlets, and <<Stream>> is automatically moved down to a new empty cell.
9. Repeat steps 1-3 to connect the other stream, **Feed 2**.




HYSYS recognizes that there is no existing stream named MixerOut, so it will create the new stream with this name.

The status indicator now displays 'Requires a product stream'. Next you will assign a product stream.

10. Move to the **Outlet** field by clicking on it, or by pressing TAB.
11. Type 'MixerOut' in the cell, then press ENTER. The status indicator now displays a green OK, indicating that the operation and attached streams are completely calculated.


Figure 1.43



HYSYS has calculated the outlet stream by combining the two inlets and flashing the mixture at the lowest pressure of the inlet streams. In this case, both inlets have the same pressure (600 psia), so the outlet stream is set to 600 psia.

12. Click the **Parameters** page.
13. In the Automatic Pressure Assignment group, leave the default setting at **Set Outlet to Lowest Inlet**.

Figure 1.44






14. To view the calculated outlet stream, click the **Worksheet** tab, then click on the **Conditions** page.


The Conditions page is a condensed Workbook page, displaying only those streams attached to the selected operation.

Figure 1.45



15. Now that the Mixer is completely known, close the view to return to the Workbook. The new operation appears in the table on the **Unit Ops** tab of the Workbook.

Figure 1.46



The table shows the operation Name, its Object Type, the attached streams (Feeds and Products), whether it is Ignored, and its Calculation Level. When you click the View UnitOps button, the property view for the currently selected operation appears. Alternatively, double-clicking on any cell (except Inlet, Outlet, and Ignored) associated with the operation also opens the Mixer property view.



You can also open the property view for a stream directly from the Unit Ops tab. When any of the Name, Object Type, Ignored or Calc. Level cells are active, the box at the bottom of the Workbook displays all streams attached to the current operation. Currently, the Name cell for MIX-100 has focus, and the box displays the three streams attached to this operation.

To open the property view for one of the streams attached to the Mixer, do **one** of the following:

- Double-click on **Feed 1** in the box at the bottom of the **Workbook**.
- Double-click on the **Inlet** cell for **MIX-100**. The property view for the first listed feed stream, in this case **Feed 1**, appears.

## Installing the Inlet Separator


Next you will install and define the inlet separator, which splits the two-phase MixerOut stream into its vapour and liquid phases.

In the Workbook, the Unit Ops tab should again be active.

1. Click the **Add UnitOps** button. The UnitOps view appears. You can also access the Unit Ops view by pressing **F12**.
2. In the Categories group, select the **Vessels** radio button.
3. In the list of Available Unit Operations, choose **Separator**.
4. Click the **Add** button. The Separator property view appears, displaying the **Connections** page on the **Design** tab.
5. In the **Name** cell, change the name to InletSep, then press **ENTER**.
6. Move to the Inlets list by clicking on the << **Stream**>> cell, or by pressing **ALT L**.
7. Open the drop-down list of available feed streams.
8. Select the stream **MixerOut** by doing one of the following:
  - Click on the stream name in the drop-down list.
  - Press the Down arrow key to highlight the stream name, then press **ENTER**.



9. Move to the **Vapour Outlet** cell by doing one of the following:
    - Click on the **Vapour Outlet** cell.
    - Press **ALT V**.
  10. To create the vapour outlet stream, type SepVap, then press **ENTER**.
  11. Click on the **Liquid Outlet** cell, type the name SepLiq, then press **ENTER**.
- The completed Connections page appears as shown in the following figure.

**Figure 1.47**


An Energy stream could be attached to heat or cool the vessel contents. For this tutorial, however, the energy stream is not required.



The Volume, Liquid Volume and Liquid Level default values generally apply only to vessels operating in dynamic mode or with reactions attached

12. Select the **Parameters** page. The current default values for Delta P, Volume, Liquid Volume and Liquid Level are acceptable.

Figure 1.48



13. To view the calculated outlet stream data, click the **Worksheet** tab, then select the **Conditions** page. The table appearing on this page is shown below.

Figure 1.49

Name	MixerOut	SepLiq	SepVap
Vapour	0.8976	0.0000	1.0000
Temperature [F]	60.00	60.00	60.00
Pressure [psia]	600.0	600.0	600.0
Molar Flow [MMSCFD]	10.00	1.024	8.976
Mass Flow [lb/hr]	2.775e+004	4564	2.318e+004
Std Ideal Liq Vol Flow [barrel/day]	4995	652.9	4342
Molar Enthalpy [Btu/lbmole]	-3.807e+004	-5.122e+004	-3.657e+004
Molar Entropy [Btu/lbmole-F]	35.66	25.87	36.77
Heat Flow [Btu/hr]	-4.180e+007	-5.756e+006	-3.605e+007

14. When finished, click the **Close** icon to close the separator property view.






Heat Exchanger Icon

## Installing the Heat Exchanger

Next, you will install is the gas/gas exchanger.

1. Ensure that the Object Palette is visible; if not, press F4.
2. On the Object Palette, double-click the **Heat Exchanger** icon.  
The Heat Exchanger property view appears. The **Connections** page on the **Design** tab is active.

Figure 1.50



3. In the **Name** field, change the operation name from its default E-100 to Gas/Gas.




You will have to create all streams except SepVap, which is an existing stream that can be selected from the Tube Side Inlet drop-down list.

Create the new streams by selecting the appropriate input field, typing the name, then pressing **ENTER**.


- Attach the inlet and Outlet streams as shown below, using the methods learned in the previous sections.

Figure 1.51



- Click the **Parameters** page.  
The **Exchanger Design (End Point)** is the acceptable default setting for the Heat Exchanger Model for this tutorial.
- Enter a pressure drop of 10 psi for both the **Tube Side Delta P** and **Shell Side Delta P**.


Figure 1.52





7. Click the **Rating** tab, then select the **Sizing** page.
8. In the Configuration group, click in the **Tube Passes per Shell** cell, then change the value to 1, to model Counter Current Flow.

Figure 1.53



9. Close the Heat Exchanger property view to return to the Workbook.
10. Click the **Material Streams** tab of the Workbook.

Notice how partial information is passed (for stream CoolGas) throughout the flowsheet. HYSYS always calculates as many properties as possible for the streams based on the available information.

Stream CoolGas has not yet been flashed, as its temperature is unknown. CoolGas is flashed later when a temperature approach is specified for the Gas/Gas heat exchanger.

Figure 1.54

The screenshot shows the 'Workbook - Case [Main]' dialog box. The 'Material Streams' tab is selected, showing a table of stream properties for Feed 1, Feed 2, MixerOut, SepVap, SepLiq, CoolGas, SalesGas, and LTSVap.

Name	Feed 1	Feed 2	MixerOut	SepVap
Vapour Fraction	0.8952	0.9013	0.8976	1.0000
Temperature [F]	60.00	60.00	60.00	60.00
Pressure [psia]	600.0	600.0	600.0	600.0
Molar Flow [MMSCFD]	6.000	4.000	10.00	8.976
Mass Flow [lb/hr]	1.675e+004	1.100e+004	2.775e+004	2.318e+004
Liquid Volume Flow [barrel/day]	3012	1983	4995	4342
Heat Flow [Btu/hr]	-2.553e+007	-1.628e+007	-4.180e+007	-3.605e+007
Name	SepLiq	CoolGas	SalesGas	LTSVap
Vapour Fraction	0.0000	<empty>	<empty>	<empty>
Temperature [F]	60.00	<empty>	<empty>	<empty>
Pressure [psia]	600.0	590.0	<empty>	<empty>
Molar Flow [MMSCFD]	1.024	8.976	<empty>	<empty>
Mass Flow [lb/hr]	4564	2.318e+004	<empty>	<empty>
Liquid Volume Flow [barrel/day]	652.9	4342	<empty>	<empty>
Heat Flow [Btu/hr]	-5.756e+006	<empty>	<empty>	<empty>



## 1.2.7 Using Workbook Features

Before installing the remaining operations, you will examine a number of Workbook features that allow you to access information quickly and change how information is displayed.


### Accessing Unit Operations from the Workbook

There are several ways to open the property view for an operation directly from the Workbook. In addition to using the Unit Ops tab, you can use the following method:

1. Click one of the Workbook streams tabs (Material Streams, Compositions or Energy Streams). The box at the bottom of the Workbook view displays the operations to which the current stream is attached.
2. For this example, click on any cell associated with the stream SepVap. The box at the bottom displays the names of the two operations, InletSep and Gas/Gas, to which this stream is attached.
3. To access the property view for either of these operations, double-click on the operation name.

Any utilities attached to the stream with the Workbook active will also be displayed in (and are accessible through) this box.

Figure 1.55





## Adding a Tab to the Workbook


When the Workbook has focus, the Workbook item appears in the HYSYS menu bar. This allows you to customize the Workbook to display specific information.

In this section you will create a new Workbook tab that displays only stream pressure, temperature, and flow.

1. Do **one** of the following:
  - From the **Workbook** menu, select **Setup**.
  - Object inspect (right-click) the Material Streams tab in the Workbook, then select **Setup** from the menu that appears.

The Workbook Setup view appears.

Figure 1.56




The four existing tabs are listed in the Workbook Pages group. When you add a new tab, it will be inserted *before* the highlighted tab (currently Material Streams).

2. In the Workbook Tabs group list, select the **Compositions** tab.




- Click the **Add** button. The New Object Type view appears.

Figure 1.57



- Click the + beside **Stream** to expand it into Material Stream and Energy Streams.
- Select the **Material Stream** and click the **OK** button. You will return to the Setup view, and the new tab appears in the list after the existing **Material Streams** tab.

Figure 1.58




- In the Object group, click in the **Name** cell and change the name for the new tab from the default Material Streams 1 to P,T,Flow to better describe the tab contents.



Next you will customize the tab by removing the irrelevant variables.

7. In the Variables group, select the first variable, Vapour Fraction.


**Figure 1.59**



8. Press and hold the CTRL key.
9. Click on the following variables: Mass Flow, Heat Flow and Molar Enthalpy. These four variables are now selected.
10. Release the CTRL key.
11. Click the **Delete** button. The unneeded variables are removed from the list. The finished Setup appears below.

Deleting variables removes them from the current Workbook tab *only*. If you want to remove variables from another tab, you must edit each tab individually.

**Figure 1.60**





12. Close the Setup view to return to the Workbook and see the new tab.

Figure 1.61

	Feed 1	Feed 2	MixerOut	SepVap
Name	Feed 1	Feed 2	MixerOut	SepVap
Temperature [F]	60.00	60.00	60.00	60.00
Pressure [psia]	600.0	600.0	600.0	600.0
Molar Flow [MMSCFD]	6.000	4.000	10.00	8.976
Std Ideal Liq Vol Flow [barrel/day]	3012	1983	4995	4342

	SepLiq	CoolGas	SalesGas	LT SVap
Name	SepLiq	CoolGas	SalesGas	LT SVap
Temperature [F]	60.00	<empty>	<empty>	<empty>
Pressure [psia]	600.0	590.0	<empty>	<empty>
Molar Flow [MMSCFD]	1.024	8.976	<empty>	<empty>
Std Ideal Liq Vol Flow [barrel/day]	652.9	4342	<empty>	<empty>

Material Streams | **P.T.Flow** | Compositions | Energy Streams | Unit Ops

FeederBlock\_Feed 1  
MDX-100

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0

13. At this point, save your case by doing **one** of the following:

- Click the **Save** icon on the toolbar.
- Select **Save** from the **File** menu.
- Press **CTRL S**.



Save Icon

## 1.2.8 Using the PFD

The PFD is the other home view used in the Simulation environment.

To open the PFD, do **one** of the following:

- Click the **PFD** icon on the toolbar.
- Press **CTRL P**, or, from the **Tools** menu, select **PFDs**. The Select PFD view appears. Select the required PFD from the list, then click the **View** button.



PFD Icon

The PFD menu option appears in the HYSYS menu bar whenever the PFD is active.







- Display the Object Inspection menu for an object by placing the cursor over it and right-clicking. This menu provides access to a number of commands associated with that particular object.
- Zoom in and out, or display the entire flowsheet in the PFD window by clicking the zoom buttons at the bottom left of the PFD view.

Some of these functions will be illustrated here; for more information, refer to the User Guide.

## Calculation Status

Before proceeding, you will examine a feature of the PFD which allows you to trace the calculation status of the objects in your flowsheet. If you recall, the status indicator at the bottom of the property view for a stream or operation displayed three different states for the object:

Indicator Status	Description
<b>Red Status</b>	A major piece of defining information is missing from the object. For example, a feed or product stream is not attached to a Separator. The status indicator is red, and an appropriate warning message appears.
<b>Yellow Status</b>	All major defining information is present, but the stream or operation has not been solved because one or more degrees of freedom is present (for example, a Cooler where the outlet stream temperature is unknown). The status indicator is yellow, and an appropriate warning message appears.
<b>Green Status</b>	The stream or operation is completely defined and solved. The status indicator is green, and an OK message appears.

Keep in mind that these are the HYSYS default colours; you may change the colours in the Session Preferences.

When you are working in the PFD, the streams and operations are also colour-coded to indicate their calculation status. The mixer and inlet separator are completely calculated, so they have a black outline. For the heat exchanger Gas/Gas, however, the conditions of the tube-side outlet and both shell-side streams are unknown, so the exchanger has a yellow outline indicating its unsolved status.

The icons for all streams installed to this point are dark blue except for the Heat Exchanger shell-side streams LTSvap and SalesGas, and tube-side outlet CoolGas.

A similar colour scheme is used to indicate the status of streams. For material streams, a dark blue icon indicates the stream has been flashed and is entirely known. A light blue icon indicates the stream cannot be flashed until some additional information is supplied. Similarly, a dark red icon indicates an energy stream with a known duty, while a purple icon indicates an unknown duty.



## Installing the Chiller

In this section you will install a chiller, which will be modeled as a Cooler. In this example you will install the operation by dropping it from the Object Palette onto the PFD.

### Adding the Chiller to the PFD

1. Ensure that the Object Palette is visible; if it is not, press **F4**. The Chiller will be added to the right of the LTS, so make some empty space available in the PFD by scrolling to the right using the horizontal scroll bar.
2. Click the **Cooler** icon on the Object Palette. If you click the wrong button, click the **Cancel** icon.
3. Position the cursor over the PFD. The cursor changes to a special cursor with a plus (+) symbol attached to it. The symbol indicates the location of the operation icon.




Cooler icon



Cancel icon

Figure 1.63




When you are in Attach mode, you will not be able to move objects in the PFD. To return to Move mode, click the Attach icon again. You can temporarily toggle between Attach and Move mode by holding down the **CTRL** key.

4. Click on the PFD where you want to “drop” the Cooler. HYSYS creates a new Cooler with a default name, E-100. The Cooler has a red status (and colour), indicating that it requires feed and product streams.

### Connecting the Chiller

1. Click the **Attach Mode** icon on the PFD toolbar to enter Attach mode.








2. Position the cursor over the right end of the CoolGas stream icon. A small transparent box appears at the cursor tip. Through the transparent box, you can see a square connection point, and a pop-up description attached to the cursor tail. The pop-up Out indicates which part of the stream is available for connection, in this case the stream outlet.
3. With the pop-up Out visible, left-click and hold. The transparent box becomes solid black, indicating that you are beginning a connection.
4. Move the cursor toward the left (inlet) side of the Cooler. A trailing line appears between the CoolGas stream icon and the cursor, and a connection point appears at the Cooler inlet.
5. Place the cursor near the connection point, and the trailing line snaps to that point. Also, a solid white box appears at the cursor tip, indicating an acceptable end point for the connection.
6. Release the left mouse button, and the connection is made to the connection point at the Cooler inlet.

## Adding Outlet and Energy Streams




If you make an incorrect connection:

1. Click the **Break Connection** icon on the PFD toolbar.
2. Move the cursor over the stream line connecting the two icons. A checkmark attached to the cursor appears, indicating an available connection to break.
3. Click once to break the connection.

1. Position the cursor over the right end of the Cooler icon. The connection point and pop-up Product appears.
4. With the pop-up visible, left-click and hold. The transparent box again becomes solid black.
5. Move the cursor to the right of the Cooler. A white stream icon appears with a trailing line attached to the Cooler outlet. The stream icon indicates that a new stream will be created after the next step is completed.
6. With the white stream icon visible, release the left mouse button. HYSYS creates a new stream with the default name 1.
7. Repeat steps 11-14 to create the Cooler energy stream, originating the connection from the arrowhead on the Cooler icon. The new stream is automatically named Q-100. The Cooler has yellow (warning) status, indicating that all necessary connections have been made but the attached streams are not entirely known.

Figure 1.64



8. Click the **Attach Mode** icon again to return to Move mode.




## Defining the Material and Energy Streams

The Cooler material streams and the energy stream are unknown at this point, so they are light blue and purple, respectively.


1. Double-click the **Cooler** icon to open its property view. On the **Connections** page, the names of the Inlet, Outlet and Energy streams that you recently attached appear in the appropriate cells.
2. In the **Name** field, change the operation name to Chiller.

Figure 1.65



3. Select the **Parameters** page.
4. In the **Delta P** field, specify a pressure drop of 10 psi.

Figure 1.66



5. When you are finished, close this view.




At this point, the Chiller has two degrees of freedom; one of these will be exhausted when HYSYS flashes the CoolGas stream after the exchanger temperature approach is specified.

To use the remaining degree of freedom, either the Chiller outlet temperature or the amount of duty in the Chiller energy stream must be specified. The amount of chilling duty which is available is unknown, so you will provide an initial guess of 0°F for the Chiller outlet temperature. Later, this temperature can be adjusted to provide the desired sales gas dew point temperature.

6. Double-click on the outlet stream icon (1) to open its property view.
7. In the **Name** field, change the name to ColdGas.
8. In the **Temperature** field, specify a temperature of 0°F.  
The remaining degree of freedom for this stream has now been used, so HYSYS flashes ColdGas to determine its remaining properties.
9. Click the **Close** button to return to the PFD.  
The Chiller still has yellow status, because the temperature of the CoolGas stream is unknown.

Figure 1.67




10. Double-click the energy stream icon (Q-100) to open its property view.  
The required chilling duty (in the Heat Flow cell) is calculated by HYSYS when the Heat Exchanger temperature approach is specified in a later section.



11. Rename this stream C3Duty, then close the view.

Figure 1.68



## Installing the LTS


Now that the chiller has been installed, the next step is to install the low-temperature separator (LTS) to separate the gas and condensed liquids in the ColdGas stream.

### Adding and Connecting the LTS



Separator icon

Multiple connection points appear because the Separator accepts multiple feed streams.



1. Make some empty space available to the right of the Chiller using the horizontal scroll bar.
2. Position the cursor over the **Separator** icon on the Object Palette.
3. Right-click and hold, then drag the cursor over the PFD to the right of the Chiller. The cursor changes to a special “bulls-eye” cursor. The bulls-eye indicates the location of the operation icon.
4. Release the right mouse button to “drop” the Separator onto the PFD. A new Separator appears with the default name V-100.
5. Click the **Attach Mode** icon on the PFD tool bar.
6. Position the cursor over the right end of the ColdGas stream icon. The connection point and pop-up Out appears.
7. With the pop-up visible, left-click and hold, then move the cursor toward the left (inlet) side of the Separator. Multiple connection points appear at the Separator inlet.
8. Place the cursor near the inlet area of the Separator. A solid white box appears at the cursor tip.
9. Release the mouse button, and the connection is made.




## Adding Connections

The Separator has two outlet streams, liquid and vapour. The vapour outlet stream LTSVap, which is the shell side inlet stream for Gas/Gas, has already been created. The liquid outlet will be a new stream.

1. In the PFD, position the cursor over the top of the Separator icon. The connection point and pop-up Vapour Product appears.
2. With the pop-up visible, left-click and hold.
3. Drag the cursor to the LTSVap stream icon. A solid white box appears when you move over the connection point.
4. Release the mouse button, and the connection is made.

Figure 1.69



5. Position the cursor over the bottom of the Separator icon. The connection point and pop-up Liquid Product appears.
6. With the pop-up visible, left-click and hold.
7. Move the cursor to the right of the Separator. A white arrow stream icon appears with a trailing line attached to the Separator liquid outlet.
8. With the stream icon visible, release the mouse button. HYSYS creates a new stream with the default name 1.
9. Click the **Attach Mode** icon to leave Attach mode.
10. Double-click on the stream icon 1 to open its property view.
11. In the **Stream Name** cell, type LTSLiQ, then press ENTER.
12. Click the **Close** icon to close the stream property view.




Attach Mode icon



13. Select **Auto Position All** from the PFD menu. Your PFD should appear similar to the one shown below.

Figure 1.70



Streams LTSVap and LTSLiq are now known, as shown by the change in their PFD colour from light blue to dark blue.

14. Double-click the icon for the new Separator (V-100) to open its property view.
15. In the **Name** field, change the name to LTS.
16. Click the **Close** icon to close this view. At this point, the outlet streams from heat exchanger Gas/Gas are still unknown.
17. Double-click on the Gas/Gas icon to open the exchanger property view.
18. Click the **Design** tab, then select the **Specs** page.

Figure 1.71

Specification	Specified Value	Current Value	Relative Error	Active	Estim.
E-100 Heat Balance	0.00 Btu/hr	<empty>	-1.0	<input checked="" type="checkbox"/>	<input type="checkbox"/>
E-100 UA	<empty>	<empty>	<empty>	<input checked="" type="checkbox"/>	<input type="checkbox"/>

Variable	Value
Temperature of CoolGas	<empty>
Temperature of SalesGas	<empty>

Design Rating Worksheet Performance Dynamics HTFS - TASC

Delete Under Specified Update Ignored



The Specs page allows you to input specifications for the Heat Exchanger and view its calculation status. The Solver group on this page shows that there are two Unknown Variables and the Number of Constraints is 1, so the remaining Degrees of Freedom is 1. HYSYS provides two default constraints in the Specifications group, although only one has a value:


Specification	Description
<b>Heat Balance</b>	The tube side and shell side duties must be equal, so the heat balance must be zero (0).
<b>UA</b>	This is the product of the overall heat transfer coefficient (U) and the area available for heat exchange (A). HYSYS does not provide a default UA value, so it is unknown at this point. It will be calculated by HYSYS when another constraint is provided.

## Adding a Heat Exchanger Specification

To exhaust the remaining degree of freedom, a 10°F minimum temperature approach to the hot side inlet of the exchanger will be specified.

1. In the Specifications group, click the **Add** button. The ExchSpec (Exchanger Specification) view appears.
2. In the **Name** cell, change the name to Hot Side Approach. The default specification in the **Type** cell is Delta Temp, which allows you to specify a temperature difference between two streams. The Stream (+) and Stream (-) cells correspond to the warmer and cooler streams, respectively.
3. In the **Stream (+)** cell, select SepVap from the drop-down list.
4. In the **Stream (-)** cell, select SalesGas from the drop-down list.
5. In the **Spec Value** cell, enter 10 (°F). The view should appear as shown in the following figure.

Figure 1.72






HYSYS will converge on both specifications and the unknown streams will be flashed.


- Click the **Close** button to return to the Gas/Gas property view. The new specification appears in the Specifications group on the **Specs** page.

Figure 1.73



- Click the **Worksheet** tab, then select the **Conditions** page to view the calculated stream properties.

Figure 1.74






Using the 10°F approach, HYSYS calculates the temperature of CoolGas as 42.9°F. All streams in the flowsheet are now completely known.

8. Click the **Performance** tab, then select the **Details** page, where HYSYS displays the Overall Performance and Detailed Performance.

Figure 1.75



Two parameters of interest are the UA and LmtD (logarithmic mean temperature difference), which HYSYS has calculated as 2.08e4 Btu/°F-hr and 22.6°F, respectively.

9. When you are finished viewing the results, click the **Close** icon to leave the Gas/Gas property view.

## Checking the Sales Gas Dew Point

The next step is to check the SalesGas stream to see if it meets a dew point temperature specification. This is to ensure no liquids form in the transmission line. A typical pipeline dew point specification is 15 °F at 800 psia, which will be used for this example.

You can test the current dew point by creating a stream with a composition identical to SalesGas, specifying the dew point pressure, and having HYSYS flash the new stream to calculate its dew point temperature. To do this you will install a Balance operation.






Balance icon


1. Double-click the **Balance** icon on the Object Palette. The property view for the new operation appears.

Figure 1.76



2. In the **Name** field, type DewPoint, then press ENTER.
3. Click in the <<Stream>> cell in the Inlet Streams table.
4. Open the drop-down list of available streams and select SalesGas.

Figure 1.77




Changes made to the vapour fraction, temperature or pressure of stream SalesDP will not affect the rest of the flowsheet. However, changes which affect SalesGas will cause SalesDP to be re-calculated because of the molar balance between these two streams.

5. Click in the <<Stream>> cell in the Outlet Streams table.
6. Create the outlet stream by typing SalesDP, then press ENTER.
7. Click the **Parameters** tab.




8. In the Balance Type group, select the **Mole** radio button.

Figure 1.78



9. Click the **Worksheet** tab. The vapour fraction and pressure of SalesDP can now be specified, and HYSYS will perform a flash calculation to determine the unknown temperature.
10. In the SalesDP column, **Vapour** cell, enter 1.0.
11. In the **Pressure** cell, enter 800 psia.  
HYSYS flashes the stream at these conditions, returning a dew point Temperature of 5.27°F, which is well within the pipeline specification of 15°F.

Figure 1.79



12. Close the view to return to the PFD.



When HYSYS created the Balance and new stream, their icons were probably placed in the far right of the PFD. If you like, you can click and drag the Balance and SalesDP icons to a more appropriate location, such as immediately to the right of the SalesGas stream.


## Installing the Second Mixer

In this section you will install a second mixer, which is used to combine the two liquid streams, SepLiq and LTSLiq, into a single feed for the Distillation Column.



Mixer icon

Multiple connection points appear because the Mixer accepts multiple feed streams.



1. In the PFD, make some empty space available to the right of the LTS using the horizontal scroll bar.
2. Click the **Mixer** button on the Object Palette.
3. In the PFD, position the cursor to the right of the LTSLiq stream icon.
4. Click to “drop” the Mixer onto the PFD. A new Mixer named MIX-101 appears.
5. Press and hold the **CTRL** key to temporarily enable **Attach** mode while you make the Mixer connections.
6. Position the cursor over the right end of the LTSLiq stream icon. The connection point and pop-up Out appears.
7. With the pop-up visible, click and drag the cursor toward the left (inlet) side of the Mixer, and multiple connection points appear at the Mixer inlet.
8. Place the cursor near the inlet area of the Mixer. When the solid white box appears at the cursor tip, release the left mouse button to make the connection.
9. Repeat the above steps to connect SepLiq to the Mixer.
10. Move the cursor over the right end of the Mixer icon. The connection point and pop-up Product appears.
11. With the pop-up visible, click and drag the cursor to the right of the Mixer. A white arrow stream icon appears.
12. With the stream icon visible, release the mouse button. HYSYS will create a new stream with the default name **1**.
13. Release the **CTRL** key to leave Attach mode.



14. Double-click on the outlet stream icon 1 to access its property view. When you created the Mixer outlet stream, HYSYS automatically combined the two inlet streams and flashed the mixture to determine the outlet conditions.
15. In the **Stream Name** cell, rename the stream to TowerFeed, then click the **Close** icon.

## Installing the Column

HYSYS has a number of pre-built column templates that you can install and customize by changing attached stream names, number of stages and default specifications.

In this section, you will install a Distillation Column.


1. From the **Tools** menu, select **Preferences**.
2. On the **Simulation** tab, **Options** page, ensure that the **Use Input Experts** checkbox is selected (checked), then close the view.
3. Double-click on the **Distillation Column** icon on the Object Palette. The first page of the Input Expert appears.



Distillation Column icon

The Input Expert is a logical sequence of input views that guide you through the initial installation of a Column. Completion of the steps will ensure that you have provided the minimum amount of information required to define the column.

Figure 1.80



When you install a column using a pre-built template, HYSYS supplies certain default information, such as the number of stages. The current active cell is Numb of Stages (Number of Stages), indicated by the thick border around this cell, and the presence of 10 (default number of stages).



Some points worth noting:

- These are theoretical stages, as the HYSYS default stage efficiency is one. If you want to specify real stages, you can change the efficiency of any or all stages later.
- The Condenser and Reboiler are considered separate from the other stages, and are not included in the Numb Stages field.

For this example, 10 theoretical stages will be used, so leave the Number of Stages at its default value.

4. Move to the Inlet Streams table by clicking on the <<Stream>> cell in the table, or by pressing TAB.
5. Open the drop-down list of available feeds by clicking it, or by pressing F2 then the Down or Up arrow key.
6. Select TowerFeed as the inlet feed stream to the column. HYSYS will supply a default feed location in the middle of the Tray Section (TS), in this case stage 5 (indicated by 5\_Main TS). This default location is used, so there is no need to change the Feed Stage.

This column has Overhead Vapour and Bottoms Liquid products, but no Overhead Liquid (distillate) product.

7. In the Condenser group, select the **Full Rflx** radio button. The distillate stream disappears. This is the same as leaving the Condenser as Partial and later specifying a zero distillate rate.
8. Enter the stream and Column names as shown in the figure below. When you are finished, the **Next** button becomes active, indicating sufficient information has been supplied to advance to the next page of the Input Expert.

Figure 1.81

**Distillation Column Input Expert**

Condenser Energy Stream: CondDuty

Column Name: DePropanizer

Inlet Streams:

Stream	Inlet Stage
TowerFeed	5_Main
<< Stream >>	

# Stages: n = 10

Optional Side Draws:

Stream	Type	Draw Stage
<< Stream >>		

Stage Numbering: ☒ Top Down ☐ Bottom Up

Condenser: ☐ Total ☐ Partial ☒ Full Rflx

Ovh Vapor Outlet: OvhD

Reboiler Energy Stream: RebDuty

Bottoms Liquid Outlet: LiquidProd


< Prev Next >

Connections (page 1 of 4) Cancel



9. Click the **Next** button to advance to the **Pressure Profile** page.
10. In the **Condenser Pressure** field, enter 200 psia
11. In the **Reboiler Pressure** field, enter 205 psia.  
The Condenser Pressure Drop can be left at its default value of zero.

Figure 1.82




12. Click the **Next** button to advance to the **Optional Estimates** page.

**Although HYSYS does not require estimates to produce a converged column, good estimates will usually result in a faster solution.**

13. Specify a **Condenser temperature** of 40 °F and a **Reboiler Temperature Estimates** of 200 °F.

Figure 1.83






In general, a Distillation Column has three default specifications, however, by specifying zero overhead liquid flow (Full Reflux Condenser) one degree of freedom was eliminated. For the two remaining default specifications, overhead Vapour Rate is an estimate only, and Reflux Ratio is an active specification.


14. Click the **Next** button to advance to the fourth and final page of the Input Expert. This page allows you to supply values for the default column specifications that HYSYS has created.
15. Enter a **Vapour Rate** of 2.0 MMSCFD and a **Reflux Ratio** of 1.0. The Flow Basis applies to the Vapour Rate, so leave it at the default of **Molar**.

Figure 1.84



16. Click the **Done** button, and the Distillation Column property view appears, displaying the **Connections** page of the **Design** tab.


Figure 1.85





17. Select the **Monitor** page.

**Figure 1.86**



The Monitor page displays the status of your column as it is being calculated, updating information with each iteration. You can also change specification values and activate or de-activate specifications used by the Column solver directly from this page.

## Adding a Column Specification

The current Degrees of Freedom is zero, indicating the column is ready to be run. The Vapour Rate you specified in the Input Expert, however, is currently an Active specification, and you want to use this only as an initial estimate for the solver for this exercise.


1. In the **Ovhd Vap Rate** row, click the **Active** checkbox to clear it, leaving the **Estimate** checkbox checked.

The Degrees of Freedom will increase to 1, indicating that another active specification is required. For this example, a 2% propane mole fraction in the bottoms liquid will be specified.



2. Select the **Specs** page. This page lists all the Active and non-Active specifications which are required to solve the column.

Figure 1.87



3. In the Column Specifications group, click the **Add** button. The Add Specs view appears.
4. From the Column Specification Types list, select **Component Fraction**.
5. Click the **Add Spec(s)** button, and the Comp Frac Spec view appears.





Figure 1.88




6. In the **Name** cell, change the specification name to Propane Fraction.




7. In the **Stage** cell, choose Reboiler from the drop-down list of available stages.

Figure 1.89



8. In the **Spec Value** cell, enter 0.02 as the liquid mole fraction specification value.
9. Click in the first cell <<**Component**>> in the Components table, and select Propane from the drop-down list of available components.

Figure 1.90



10. Close this view to return to the Column property view.

HYSYS automatically made the new specification active when you created it.


The new specification appears in the Column Specifications list on the **Specs** page.

11. Return to the **Monitor** page. The new specification may not be visible unless you scroll down the table because it has been placed at the bottom of the Specifications list.



12. Click the **Group Active** button to bring the new specification to the top of the list, directly under the other Active specification.

Figure 1.91



The Degrees of Freedom has returned to zero, so the column is ready to be calculated.



## Running the Column


1. Click the **Run** button to begin calculations. The information displayed on the **Monitor** page is updated with each iteration. The column converges quickly, in three iterations.

The table in the Optional Checks group displays the Iteration number, Step size, and Equilibrium error and Heat/Spec error.

The column temperature profile appears in the Profile group. You can view the pressure or flow profiles by selecting the appropriate radio button


The status indicator has changed from Unconverged to Converged.

Figure 1.92



2. Click the **Performance** tab, then select the **Column Profiles** page to access a more detailed stage summary.

Figure 1.93





## Accessing the Column Sub-flowsheet

When considering the column, you might want to focus only on the column sub-flowsheet. You can do this by entering the column environment.

1. Click the **Column Environment** button at the bottom of the property view.
2. In this environment you can do the following:
  - Click the **PFD** icon to view the column sub-flowsheet PFD.



PFD icon




Workbook icon



Column Runner icon

Figure 1.94





- Click the **Workbook** icon to view a Workbook for the column sub-flowsheet objects.

Figure 1.95

Name	Reflux	To Condenser	Boilup	To Reboiler	Overhd
Vapour Fraction	0.0000	1.0000	1.0000	0.0000	1.0000
Temperature [F]	48.74	84.42	190.6	187.8	48.74
Pressure [psia]	200.0	200.0	205.0	205.0	200.0
Molar Flow [MMSCFD]	2.350	4.700	4.956	5.588	2.350
Mass Flow [lb/hr]	1.115e+004	1.926e+004	3.134e+004	3.536e+004	8110
Liquid Volume Flow [barrel/day]	1561	2908	3764	4245	1348
Heat Flow [Btu/hr]	-1.359e+007	-2.203e+007	-2.927e+007	-3.702e+007	-1.034e+007

Name	LiquidProd	TowerFeed	New
Vapour Fraction	0.0000	0.0187	
Temperature [F]	190.6	20.84	
Pressure [psia]	205.0	580.0	
Molar Flow [MMSCFD]	0.6320	2.982	
Mass Flow [lb/hr]	4014	1.212e+004	
Liquid Volume Flow [barrel/day]	480.4	1828	

Material Streams | Compositions | Energy Streams | Unit Ops

Main TS  
Condenser

☐ Show Name Only  
Number of Hidden Objects: 0



Enter Parent Simulation  
Environment icon

- Click the **Column Runner** icon to access the inside column property view. This property view is essentially the same as the outside, or main flowsheet, property view.
- When you are finished in the column environment, return to the main flowsheet by clicking the **Enter Parent Simulation Environment** icon in the tool bar or the **Parent Environment** button on the column Worksheet view.



## 1.2.9 Viewing and Analyzing Results

1. Open the Workbook for the main case to access the calculated results for all streams and operations.
2. Click the **Material Streams** tab.

Figure 1.96

Name	Feed 1	Feed 2	MixerOut	SepVap	SepLiq	CoolGas	SalesGas
Vapour Fraction	0.8952	0.9013	0.8976	1.0000	0.0000	0.9388	1.0000
Temperature [F]	60.00	60.00	60.00	60.00	60.00	42.97	50.00
Pressure [psia]	600.0	600.0	600.0	600.0	600.0	590.0	570.0
Molar Flow [MMSCFD]	6.000	4.000	10.00	8.976	1.024	8.976	7.018
Mass Flow [lb/hr]	1.675e+004	1.100e+004	2.775e+004	2.318e+004	4564	2.318e+004	1.562e+004
Liquid Volume Flow [barrel/day]	3012	1983	4995	4342	652.9	4342	3167
Heat Flow [Btu/hr]	-2.553e+007	-1.628e+007	-4.180e+007	-3.605e+007	-5.756e+006	-3.652e+007	-2.678e+007

Name	LTSVap	CoolGas	LTSLiq	SalesDP	TowerFeed	Ovhd	LiquidProd
Vapour Fraction	1.0000	0.7818	0.0000	1.0000	0.0187	1.0000	0.0000
Temperature [F]	0.0000	0.0000	0.0000	5.269	20.84	48.74	190.6
Pressure [psia]	580.0	580.0	580.0	800.0	580.0	200.0	205.0
Molar Flow [MMSCFD]	7.018	8.976	1.959	7.018	2.982	2.350	0.6320
Mass Flow [lb/hr]	1.562e+004	2.318e+004	7561	1.562e+004	1.212e+004	8110	4014
Liquid Volume Flow [barrel/day]	3167	4342	1175	3167	1828	1348	480.4
Heat Flow [Btu/hr]	-2.725e+007	-3.769e+007	-1.043e+007	-2.744e+007	-1.619e+007	-1.034e+007	-4.185e+006

Material Streams | P,T,Flow | Compositions | Energy Streams | Unit Ops

FeederBlock\_Feed 1  
MX-100

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0

3. Click the **Compositions** tab.

Figure 1.97

Name	Feed 1	Feed 2	MixerOut	SepVap	SepLiq	CoolGas	SalesGas
Comp Mole Frac (Nitrogen)	0.0100	0.0179	0.0132	0.0145	0.0017	0.0145	0.0179
Comp Mole Frac (CO2)	0.0100	0.0000	0.0060	0.0063	0.0034	0.0063	0.0066
Comp Mole Frac (Methane)	0.6000	0.6244	0.6098	0.6576	0.1905	0.6576	0.7664
Comp Mole Frac (Ethane)	0.2000	0.1666	0.1866	0.1846	0.2044	0.1846	0.1565
Comp Mole Frac (Propane)	0.1000	0.1136	0.1054	0.0877	0.2612	0.0877	0.0414
Comp Mole Frac (i-Butane)	0.0400	0.0431	0.0412	0.0272	0.1640	0.0272	0.0070
Comp Mole Frac (n-Butane)	0.0400	0.0345	0.0378	0.0222	0.1748	0.0222	0.0043

Name	LTSVap	CoolGas	LTSLiq	SalesDP	TowerFeed	Ovhd	LiquidProd
Comp Mole Frac (Nitrogen)	0.0179	0.0145	0.0021	0.0179	0.0020	0.0025	0.0000
Comp Mole Frac (CO2)	0.0066	0.0063	0.0053	0.0066	0.0046	0.0059	0.0000
Comp Mole Frac (Methane)	0.7664	0.6576	0.2677	0.7664	0.2412	0.3061	0.0000
Comp Mole Frac (Ethane)	0.1565	0.1846	0.2854	0.1565	0.2576	0.3269	0.0000
Comp Mole Frac (Propane)	0.0414	0.0877	0.2534	0.0414	0.2561	0.3196	0.0200
Comp Mole Frac (i-Butane)	0.0070	0.0272	0.0998	0.0070	0.1218	0.0339	0.4490
Comp Mole Frac (n-Butane)	0.0043	0.0222	0.0862	0.0043	0.1166	0.0052	0.5309

Material Streams | P,T,Flow | **Compositions** | Energy Streams | Unit Ops

FeederBlock\_Feed 1  
MX-100

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0



## Using the Object Navigator

In this section, you will use the Object Navigator to view properties for a particular stream or operation. The Object Navigator allows you to quickly access the property view for any stream or unit operation at any time during the simulation.




Navigator icon

1. To open the Navigator, do **one** of the following:
  - Press **F3**.
  - From the **Flowsheet** menu, select **Find Object**.
  - Click the **Navigator** icon.

The Object Navigator view appears:

Figure 1.98



The UnitOps radio button in the Filter group is currently selected, so only the Unit Operations appear in the list of available objects.

2. To open a property view, select the operation in the list, then click the **View** button, or double-click on the operation.
3. To change which objects appear, select a different radio button in the Filter group. To list all streams and unit operations, select the **All** button.
4. You can also search for an object by clicking the **Find** button. When the Find Object view appears, enter the Object Name, then click the **OK** button. HYSYS opens the property view for the object.
5. When you are done, close the Object Navigator view and any property views you opened.

You can start or end the search string with an asterisk (\*), which acts as a wildcard character. This lets you find multiple objects with one search. For example, searching for VLV\* will open the property view for all objects with VLV at the beginning of their name.



## Using the Databook

The HYSYS Databook provides you with a convenient way to examine your flowsheet in more detail. You can use the Databook to monitor key variables under a variety of process scenarios, and view the results in a tabular or graphical format.

For this example, the effects of LTS temperature on the Sales Gas dew point and flow rate, and the Liquid Product flow rate will be examined.


## Defining the Key Variables

Before opening the Databook, close the Object Navigator or any property view you might have opened using the Navigator.

1. To open the Databook, do **one** of the following:
  - Press **CTRL D**.
  - Open the **Tools** menu, and Select **Databook**.

The Databook appears as shown below.

Figure 1.99



2. Click the **Variables** tab. Here you will add the key variables to the Databook.




- Click the **Insert** button. The Variable Navigator view appears.

The Variable Navigator is used extensively in HYSYS for locating and selecting variables.


The Navigator operates in a left-to-right manner. The selected Flowsheet determines the Object list; the chosen Object dictates the Variable list; the selected Variable determines whether any Variable Specifics are available.

Figure 1.100



- In the Object Filter group, select the **UnitOps** radio button. The Object list will be filtered to show unit operations only.
- In the Object list, select **LTS**. The Variable list available for the LTS appears to the right of the Object list.
- In the Variable list, select **Vessel Temperature**. HYSYS displays this variable name in the **Variable Description** field.


Figure 1.101





7. Click the **OK** button to add this variable to the Databook.  
The new variable Vessel Temperature appears in the Databook.


Figure 1.102



Continue adding variables to the Databook.

8. Click the **Insert** button, and the Variable Navigator reappears.
9. In the Object Filter group, select the **Streams** radio button. The Object list is filtered to show streams only.
10. In the Object list, select SalesDP. The Variables list available for material streams appears to the right of the Object list.
11. In the Variable list, select Temperature.
12. In the Variable Description field, change description to Dew Point, then click the **Add** button. The variable now appears in the Databook, and the Variable Navigator view remains open.

Figure 1.103






13. Repeat the previous steps to add the following variables to the Databook:
- **Sales Gas** stream; **Molar Flow** variable; change the Variable Description to **Sales Gas Production**
  - **LiquidProd** stream; **Liq Vol Flow@Std Cond** variable; change the Variable Description to **Liquid Production**

The completed Variables tab of the Databook appears as shown below.

Figure 1.104




## Creating the Data Table

In this section you will create a data table to display the variables.

1. Click the **Process Data Tables** tab.
2. In the Available Process Data Tables group, click the **Add** button. HYSYS creates a new table with the default name ProcData1.

Figure 1.105





3. In the **Process Data Table** field, change the name to Key Variables. The four variables that were added to the Databook appear in the table on this tab.
4. Activate each variable by clicking on the corresponding **Show** checkbox.

Figure 1.106

Object	Variable	Show
LTS	Vessel Temperature	<input checked="" type="checkbox"/>
SalesDP	DewPoint	<input checked="" type="checkbox"/>
SalesGas	Sales Gas Production	<input checked="" type="checkbox"/>
LiquidProd	Liquid Production	<input checked="" type="checkbox"/>

5. Click the **View** button to view the Key Variables Data table, which appears below.

Figure 1.107

Key Variables Data					
Object	Variable	Value	Units	Tag	Access Mode
LTS	Vessel Temperature	0.0000	F	No Tag	No Transfer
SalesDP	DewPoint	5.269	F	No Tag	No Transfer
SalesGas	Sales Gas Production	7.018	MMSCFD	No Tag	No Transfer
LiquidProd	Liquid Production	479.7	barrel/day	No Tag	No Transfer

View Databook...

You will access this table again later to demonstrate how its results are updated whenever a flowsheet change is made.

6. For now, click the **Minimize** button in the upper right corner of the Key Variables Data view. HYSYS reduces the view to an icon and places it at the bottom of the Desktop.


## Using the Data Recorder

In this section you will use the Data Recorder to automatically record the current values of the key variables before making any changes to the flowsheet.



1. From the **Tools** menu, select **Databook**.
2. Click the **Data Recorder** tab.


Figure 1.108



When using the Data Recorder, you first must create a Scenario containing one or more of the key variables, then record the variables in their current state.

3. In the Available Scenarios group, click the **Add** button. HYSYS creates a new scenario with the default name Scenario 1.
4. In the table, activate each variable by clicking on the corresponding **Include** checkbox.

Figure 1.109




5. Click the **Record** button to record the variables in their current state. The New Solved State view appears, prompting you for the name of the new state.



6. Enter the new name Base Case, then click **OK**. You return to the Databook.
7. In the Available Display group, select the **Table** radio button.
8. Click the **View** button. The Data Recorder appears, displaying the values of the key variables in their current state.

Figure 1.110



Now you can make the necessary flowsheet changes and these current values remain as a permanent record in the Data Recorder unless you choose to erase them.

9. Click the **Minimize** button to reduce the Data Recorder to an icon.
10. Click the **Restore Up** icon on the Key Variables Data view to restore the view to its original size.

## Modifying the ColdGas Stream

In this section, you will change the temperature of stream ColdGas (which determines the LTS temperature) and view the changes in the process data table.




Navigator icon

1. Click the **Navigator** icon on the toolbar. The Object Navigator view appears
2. In the Filter group, select the **Streams** radio button.




- In the Streams list, select ColdGas, then click the View button. The ColdGas property view appears.

Figure 1.111



- Ensure that you are on the **Worksheet** tab, **Conditions** page of the property view.
- Arrange the two views as shown below by clicking and dragging on their title bars.

Figure 1.112






Currently, the LTS temperature is 0°F. The key variables will be checked at 10°F.

- In the ColdGas Temperature cell, enter 10. HYSYS automatically recalculates the flowsheet. The new results are shown below.

Figure 1.113



The change in Temperature generates the following results:

- The Sales Gas flow rate has increased.
  - The Liquid Product flow rate has decreased.
  - The sales gas dew point has increased to 15.9°F. This temperature no longer satisfies the dew point specification of 15°F.
- Click the **Close** button on the ColdGas stream property view to return to the Databook.

## Recording the New Variables in the Databook


In this section you will record the key variables in their new state.

- Click the **Data Recorder** tab in the Databook.
- Click the **Record** button, and the New Solved State view appears. HYSYS provides you with the default name State 2 for the new state.
- Change the name to 10 F in LTS, then click the **OK** button to accept the new name.



- Click the **View** button and the Data Recorder appears, displaying the new values of the variables.

Figure 1.114



- Click the **Close** icon on the Data Recorder, then on the Databook and finally on the Key Variables Table.
- Save the case.

The basic simulation for this example has now been completed. You can continue with this example by proceeding to the Optional Study sections, or you can begin building your own simulation case. In the Optional Study, you will use some of the other tools available in HYSYS to examine the process in more detail.

## 1.2.10 Optional Study

In the following sections, the effects of the LTS temperature on the SalesGas dew point and heating value are determined. Before proceeding, re-specify the temperature of ColdGas back to its original value of 0°F:



Workbook icon

- Click the Workbook icon on the toolbar.
- On the **Material Streams** tab of the Workbook, click in the **Temperature** cell for the ColdGas stream.
- Type 0, then press the ENTER key.



## Using the Spreadsheet

HYSYS has a Spreadsheet operation that allows you to import stream or operation variables, perform calculations, and export calculated results.




Spreadsheet icon

### Accessing the Spreadsheet

1. To install a Spreadsheet and display its property view, double-click the **Spreadsheet** icon in the Object Palette.

Figure 1.115



2. On the **Connections** tab, change the spreadsheet name to Heating Value.

The heating value of the sales gas is calculated by importing the stream composition into the Spreadsheet then multiplying the mole fraction of each component by its individual heating value.




## Importing Variables - First Method

In this section you will import variables on the Connections tab.

1. Click the **Add Import** button, and the Select Import view appears.
2. Choose the SalesGas Object, Comp Mole Frac Variable and Methane Variable Specific as shown.


NO<sub>2</sub> and CO<sub>2</sub> are not included in the calculation as their individual heating values are negligible.

Figure 1.116



3. Click the **OK** button.
4. Click the **Add Import** button again, then select the SalesGas Object, Comp Mole Frac Variable and Ethane Variable Specific. Click the **OK** button.
5. Repeat step 4 to add the Propane Variable Specific. For illustration purposes, the two remaining components will be added later using an alternative import method. HYSYS assigned the imported variables to Spreadsheet cells A1 through A3, by default.
6. Change the cell locations to B3 through B5 as shown in the following figure; the reason for doing so will become apparent on the Spreadsheet tab.

Figure 1.117





The HYSYS Spreadsheet behaves similarly to commercial spreadsheet packages; you enter data and formulas in the cells, and calculated results are returned.

7. No information is required on the Parameters and Formulas tabs, so click the **Spreadsheet** tab.
8. Enter the column headings as shown in the table below. You can move to a cell by clicking it, or by pressing the arrow keys.


Column/Row	Heading
A1	Component
B1	Mole Fraction
C1	Comp Heat Value
D1	Total Heat Value

9. Enter the components in the Component column as shown as shown in the table below.

Row	Component
3	C1
4	C2
5	C3
6	iC4
7	nC4

10. Enter the component net heating values in the Comp Heat Value column as shown in the figure below.

**Figure 1.118**





## Importing Variables - Second Method

The next task is to import the remaining two variables' mole fractions in the Sales Gas.

1. Position the cursor over the empty Spreadsheet cell (B6) reserved for the iC4 mole fraction.
2. Right-click once. From the menu that appears, select **Import Variable**. The Select Import for cell view appears.
3. Select the SalesGas Object, Comp Mole Frac Variable, and i-Butane Variable Specific.
4. Click the **OK** button to accept the input and close the view.
5. Import the mole fraction for **nC4**.
  - Position the cursor over cell **B7**.
  - Right-click once, and select **Import Variable**.
  - Select the SalesGas Object, Comp Mole Frac Variable, and n-Butane Variable Specific.

View Associated Object  
Import Variable  
Export Formula Result  
Disconnect Import/Export

## Entering Formulas

The next task is entering the formulas for calculating the component and total sales gas heating values.

1. Click in cell **D3**.
2. Type  $+b3*c3$ , then press ENTER. This multiplies the Methane mole fraction by its Net Heating Value.
3. Enter the following formulas in cells **D4** through **D7**.


All formulas must be preceded by a +.

Cell	Formula
D4	$+b4*c4$
D5	$+b5*c5$
D6	$+b6*c6$
D7	$+b7*c7$



4. The table should appear as shown in the figure below.

Figure 1.119




Current Cell: Imported From: SalesGas Exportable: ☐  
 B5 Variable: Comp Mole Frac (Propane) Angles in:

	A	B	C	D
	Component	Mole Fraction	Comp Heat Value	Total Heat Value
1				
2				
3	C1	0.7664	909.4	6.9693e+02
4	C2	0.1565	1619	2.5333e+02
5	C3	0.0414	2315	9.5887e+01
6	iC4	0.0070	3000	2.0945e+01
7	nC4	0.0043	3011	1.2932e+01
8				
9				
10				

Connections Parameters Formulas **Spreadsheet** Calculation Order Yes  
 Delete Function Help... Spreadsheet Only... ☐ Ignored

5. Click in cell C9, and enter the label Sales Gas NHV.  
 6. Click in cell D9.  
 7. Enter +d3+d4+d5+d6+d7 in cell D9 to sum the individual heating values. The result is the NHV of SalesGas in Btu/scf.

Figure 1.120



Current Cell: Variable Type: Vapour Fraction Exportable: ☒  
 D9 Variable: Angles in: Rad  
 +d3+d4+d5+d6+d7

	A	B	C	D
	Component	Mole Fraction	Comp Heat Value	Total Heat Value
1				
2				
3	C1	0.7664	909.4	6.9693e+02
4	C2	0.1565	1619	2.5333e+02
5	C3	0.0414	2315	9.5887e+01
6	iC4	0.0070	3000	2.0945e+01
7	nC4	0.0043	3011	1.2932e+01
8				
9			Sales Gas NHV	1.0800e+03
10				

Connections Parameters Formulas **Spreadsheet** Calculation Order Yes  
 Delete Function Help... Spreadsheet Only... ☐ Ignored



To add the value of Sales Gas NHV to the Databook:

1. Click the **Parameters** tab of the Heating Value property view.
2. In the Exportable Cells table, enter a Variable Name for cell **D9** (for example NHV).
3. Close the Heating Value property view.
4. Open the Databook by pressing **CTRL D**.
5. On the **Variables** tab, insert the variable, selecting the Heating Value operation as the Object and NHV as the variable.

The Adjust operation performs automatic trial-and-error calculations until a target value is reached.

The current heating value of the sales gas is 1080 Btu/scf. Whenever flowsheet changes are made that result in the re-calculation of the stream SalesGas, the compositional changes will be automatically transferred to the Spreadsheet, and the heating value updated accordingly.

8. Click the **Close** button to continue with the study.

## Installing an Adjust for Calculating the LTS Temperature

Suppose the market price of your liquid product is currently unfavourable and you want to raise the LTS temperature to leave more of the heavier components in the gas phase. This will increase the sales gas heating value, resulting in a bonus from the transmission company. The sales gas must, however, still comply with the dew point specification.

An Adjust operation can be used to adjust the temperature of the LTS (ColdGas stream) until the sales gas dew point is within a few degrees of the pipeline specification. In effect, this increases the gas heating value while still satisfying the dew point criteria.

## Installing, Connecting and Defining the Adjust




Adjust icon

1. Click the PFD icon to display the PFD. The Object Palette should also be visible; if not, press **F4**.
2. Click the **Adjust** icon on the Object Palette.
3. Position the cursor on the PFD to the right of the SalesDP stream icon.
4. Click to 'drop' the Adjust icon onto the PFD. A new ADJUST object appears with the default name **ADJ-1**.
5. Click the **Attach Mode** icon on the PFD toolbar to enter Attach mode.
6. Position the cursor over the left end of the ADJ-1 icon. The connection point and pop-up Adjusted Object appears.
7. With the pop-up visible, left-click and drag toward the ColdGas stream icon.



8. When the solid white box appears on the ColdGas stream, release the mouse button. The Select Adjusted Variable view appears.


Figure 1.121




At this point, HYSYS knows that the ColdGas should be adjusted in some way to meet the required target. An adjustable variable for the ColdGas must now be selected from the Select Adjusted Variable view.

9. From the Variable list, select Temperature.
10. Click the OK button.
11. Position the cursor over the right corner of the ADJ-1 icon. The connection point and pop-up Target Object appears.
12. With the pop-up visible, left-click and drag toward the SalesDP stream icon.
13. When the solid white box appears at the cursor tip, release the mouse button. The Select Target Variable view appears.

Figure 1.122








14. From the Variable list, select Temperature.
15. Click the **OK** button.
16. Click the **Attach Mode** icon to leave Attach mode.
17. Double-click the ADJ-1 icon to open its property view. The connections made in the PFD have been transferred to the appropriate cells in the property view.

## Adjusting the Target Variable

The next task is to provide a value for the target variable, in this case the dew point temperature. A 5°F safety margin will be used on the pipeline specification of 15°F, so the desired dew point is 10°F.

1. In the **Specified Target Value** field, enter 10°F.

**Figure 1.123**




2. Click the **Parameters** tab.
3. In the **Tolerance** cell, enter 0.1°F.




4. In the **Step Size** cell, enter 5°F. No values will be entered in the **Minimum** and **Maximum** field, as these are optional parameters.

Figure 1.124



5. Click the **Monitor** tab. This allows you to view the calculations.
6. Click the **Start** button. The Adjust converges on the target value within the specified tolerance in five iterations. An LTS temperature (adjusted variable) of 4.4°F gives a sales gas dew point (target variable) of 10°F.

Figure 1.125






The Adjust has changed the LTS temperature from the original value of 0°F to 4.4°F. The new sales gas heating value can now be compared to the previous value to see the effect of this change.

7. Click the **Close** icon on the Adjust property view.

## Results of the Study

Open the Workbook to access the calculated results for the entire flowsheet. The Material Streams and Compositions tabs of the Workbook appear below.

Figure 1.126






## 1.3 Dynamic Simulation

You can continue to this dynamic section with the case you built during the steady state section, or you can open the completed steady state version (which is the starting point for this dynamic section) called **TUTOR1.hsc** in the HYSYS\Samples directory.

In this tutorial, the dynamic capabilities of HYSYS will be incorporated into a basic steady state gas plant model. The plant takes two different natural gas streams containing carbon dioxide and methane through n-butane and combines and processes them in a simple refrigeration system. A series of separators and coolers removes the heavier hydrocarbon components from the natural gas stream, allowing it to meet a pipeline dew point specification. The heavier liquid component of the gas stream is processed in a depropanizer column, yielding a liquid product with a specified propane content.

**Figure 1.127**



This is only one method of preparing a steady state case for Dynamic mode.

The Dynamics Assistant will be used to make pressure-flow specifications and size pieces of equipment in the simulation flowsheet. It is also possible to set your own pressure-flow specifications and size the equipment without the aid of the Dynamics Assistant.

A completed dynamic case has been pre-built and is called **dyntut1.hsc** in the HYSYS\Samples directory.

This tutorial will comprehensively guide you through the steps required to add dynamic functionality to a steady state gas plant simulation. To help you navigate these detailed procedures, the following milestones have been established for this tutorial:

1. Modify the steady state model so that a pressure-flow relation exists between each unit operation.
2. Implement a tray sizing utility for sizing the Depropanizer column.



In this Tutorial, you will follow this basic procedure in building the dynamic model.

3. Use the Dynamics Assistant to set pressure flow specifications and size the equipment in the simulation case.
4. Install and define the appropriate controllers.
5. Set up the Databook. Make changes to key variables in the process and observe the dynamic behaviour of the model.

## 1.3.1 Modifying the Steady State Flowsheet

It is necessary to add unit operations such as valves, heat exchangers, or pumps, to define pressure flow relations between unit operations that have no pressure flow relation. In this tutorial, valve operations will be added between Separator, Mixer and Column operations.

A Heater operation will also be added between the Mixer and Column operation for dynamic simulation purposes. Installing a heater allows you to vary the temperature of the feed entering the column.

Valves will be added to the following material streams:

- SepLiq
- LTSLiq
- TowerFeed
- LiquidProd

The first task is to set the session preferences.

1. Open the pre-built case file **TUTOR1.hsc**.
2. From the **Tools** menu, select **Preferences**. The Session Preferences view appears.
3. Click the **Variables** tab, then select the **Units** page.
4. In the Available Unit Sets group list, select **Field**.


The steady state Gas Processing simulation file TUTOR1.hsc is located in your HYSYS\Samples directory.

In the Dynamic simulation part of this tutorial you will work with the default Field units.




5. Click the **Simulation** tab, then select the **Dynamics** page.

Figure 1.128



6. In the Assistant group, uncheck both the **Perform checks when switching to dynamics or starting the integrator** and the **Set dynamic stream specifications in the background** checkboxes.

Figure 1.129



Close icon

7. Close the Session Preferences view along with all the open views on the HYSYS desktop (except for the PFD view) by clicking the **Close** icon in the top right corner of each view.



In the PFD, the stream pressure for Feed 2 will be deleted so that it will be calculated by the MIX-100 in dynamic mode.

8. Double-click the Feed 2 stream icon to open its property view.
9. On the **Conditions** page of the **Worksheet** tab, click in the **Pressure** cell, then press **DELETE** to remove the stream pressure.
10. Close the stream property view.

Next you will change the pressure setting for the MIX-100 so that the whole PFD can be simulated.

11. Double-click the MIX-100 icon to open its property view.
12. On the **Design** tab, select the **Parameters** page.
13. In the Automatic Pressure Assignment group, click the **Equalize All** radio button.
14. Close the MIX-100 property view.

Next you will insert a valve operation between the SepLiq stream and the MIX-101 unit operation.



Break Connection icon

15. Click the **Break Connection** icon in the PFD toolbar.
16. Break the SepLiq stream by doing the following:
  - Position the mouse pointer over the SepLiq stream to the right of the stream arrow.
  - When the mouse pointer has a checkmark beside it, left-click and the stream will disconnect from the MIX-101.
17. Open the Object Palette by pressing **F4**.
18. On the Object Palette, right-click and hold on the **Valve** icon.
19. While holding the right mouse button, drag the cursor over the PFD. The mouse pointer becomes a bullseye.
20. Position the bullseye pointer beside the SepLiq stream and release the mouse button.
21. A Valve icon named VLV-100 appears.
22. Double-click the VLV-100 icon on the PFD to open its property view.
23. In the valve property view, specify the following connections:



Valve icon

Tab [Page]	In this cell...	Enter...
<b>Design [Connections]</b>	Name	Sep Valve
	Inlet	SepLiq
	Outlet	SepExit
<b>Design [Parameters]</b>	Delta P	25 psi





Attach Mode icon

24. Click the **Close** icon to close the valve property view.
25. Connect the SepExit stream to the inlet of the MIX-101 unit operation by doing the following:
  - Click the PFD **Attach Mode** icon.
  - Position the mouse pointer at the tip of the SepExit stream arrow. A white box appears.
  - Click and drag the pointer to the left side of MIX-101. A white box appears, indicating a connection point.
  - Release the mouse button to complete the connection.
  - Click the **Attach Mode** icon again to exit from the attach mode.

Next you will insert a valve operation between the LTSLiq stream and the MIX-101 unit operation.

26. Break the line between the LTSLiq stream and the MIX-101 unit operation.
  - Click the **Break Connection** icon in the tool bar.
  - Click to the right of the arrow on the LTSLiq stream.
27. Install a second valve operation.
  - On the Object Palette, right-click the **Valve** icon.
  - Drag the cursor to the right of the LTSLiq stream.
  - Release the mouse button.
28. Double-click the valve icon to open its property view.
29. Specify the following connections:

Tab [Page]	In this cell...	Enter...
<b>Design [Connections]</b>	Name	LTS Valve
	Inlet	LTSLiq
	Outlet	LTSExit
<b>Design [Parameters]</b>	Delta P	5 psi

30. Close the valve property view.



31. Attach the LTSExit stream to the MIX-101 unit operation.

- Click the **Attach Mode** icon
- Move the cursor over the LTSExit stream icon. A white box appears.
- Click and drag the cursor to the inlet side of the MIX-101 icon. A white box appears, indicating a connection point.
- Release the mouse button to complete the connection.
- Click the **Attach Mode** icon again to exit the attach mode.

Next you will add a valve operation between the MIX-101 unit operation and the TowerFeed stream.

32. Break the line between the TowerFeed stream and the MIX-101 unit operation. Be sure to break the line to the left of the TowerFeed stream arrow.

33. Install a third valve operation with the following connections:

Tab [Page]	In this cell...	Enter...
<b>Design [Connections]</b>	Name	Tower Valve
	Inlet	TowerIn
	Outlet	TowerInlet
<b>Design [Parameters]</b>	Delta P	363 psi

34. Close the valve property view.

35. Click the **Attach Mode** icon, then connect the TowerIn stream to the exit of the MIX-101 unit operation. Exit the attach mode.

36. Install a Heater operation and position it near the Tower Valve and the DePropanizer.

- In the Object Palette, click once on the **Heater** icon.
- In the PFD, click where you want to insert the heater.

37. Open the heater property view and specify the following connections:

Tab [Page]	In this cell...	Enter...
<b>Design [Connections]</b>	Name	Heater
	Inlet	TowerInlet
	Outlet	TowerFeed
	Energy	Heater Q
<b>Design [Parameters]</b>	Delta P	9 psi

38. In the heater property view, click the **Worksheet** tab, then select the **Conditions** page.

You can use the scroll bars to navigate around the PFD. You can also use the PAGE UP and PAGE DOWN keys to zoom in and out of the PFD, respectively.



39. In the **Temperature** cell of the TowerFeed stream, enter 24.73°F.

Figure 1.130

Worksheet	Name	TowerInlet	TowerFeed	Heater Q
Conditions	Vapour	0.2633	0.3967	<empty>
	Temperature [F]	-6.448	24.73	<empty>
Properties	Pressure [psia]	212.0	203.0	<empty>
	Molar Flow [lbmole/hr]	310.6	310.6	<empty>
Composition	Mass Flow [lb/hr]	1.162e+004	1.162e+004	<empty>
	Std Ideal Liq Vol Flow [barrel/day]	1742	1742	<empty>
PF Specs	Molar Enthalpy [Btu/lbmole]	-4.963e+004	-4.832e+004	<empty>
	Molar Entropy [Btu/lbmole-F]	26.18	29.00	<empty>
	Heat Flow [Btu/hr]	-1.542e+007	-1.501e+007	4.064e+005

Design Rating **Worksheet** Performance Dynamics

Delete OK ☐ Ignored

When considering pieces of equipment associated with a column, it may be necessary to enter the Column sub-flowsheet environment.

40. Close the Heater property view.

Next you will add a valve to the LiquidProd stream in the Column sub-flowsheet.

41. Double-click the DePropanizer column to open its property view.

Figure 1.131

Column: DePropanizer / COL1 Fluid Pkg: Basis-1 / PengRobinson

Parameters

Steady State Profiles

Optional Estimates

	Stage	Pressure [psia]	Temp [F]	Net Liquid [lbmole/hr]	Net Vapour [lbmole/hr]
Condenser	1	200.0	40.00	244.3	244.3
1_Main TS	2	200.0	88.42	248.9	488.5
2_Main TS	3	200.6	101.4	244.4	493.1
3_Main TS	4	201.1	109.0	240.5	488.7
4_Main TS	5	201.7	114.2	237.8	484.8
5_Main TS	6	202.2	117.8	450.2	482.0
6_Main TS	7	202.8	156.0	496.4	383.9
7_Main TS	8	203.3	170.5	510.6	430.1
8_Main TS	9	203.9	178.7	516.9	444.2
9_Main TS	10	204.4	184.2	520.4	450.6
10_Main TS	11	205.0	188.1	522.5	454.0
Reboiler	12	205.0	200.0	66.34	456.1

Flow Basis: ☒ Molar ☐ Mass ☐ Volume

Pressure vs. Tray Number

Update from Solution Clear Tray Clear All Trays Lock Unlock Stream Estimates...

Design **Parameters** Side Ops Rating Worksheet Performance Flowsheet Reactions Dynamics

Delete Column Environment... Run Reset **Converged** ☒ Update Outlets ☐ Ignored



42. Click the **Column Environment** button to enter the Column Sub-flowsheet environment.

Next you will inset a valve operation between the LiquidProd stream and the Reboiler unit operation.

43. In the PFD of the column sub-flowsheet, break the connection between the LiquidProd stream and the Reboiler unit operation.
44. Press F4 to open the Object Palette.
45. Install a valve operation between the Reboiler and the LiquidProd stream icon. Move the LiquidProd stream to make room if required.
46. Open the valve property view and specify the following connections:


Tab [Page]	In this cell...	Enter...
Design [Connections]	Name	Reboil Valve
	Inlet	LiquidExit
	Outlet	LiquidProd
Design [Parameters]	Delta P	25 psi

47. Close the valve property view.
48. Click the **Attach Mode** icon, then connect the LiquidExit stream to the liquid exit connection point of the Reboiler. Exit the attach mode when you are done.
49. Click the **Run Column Solver** icon in the tool bar. The column will solve with the existing column specifications and the added valve unit operations.



Run Column Solver icon

Figure 1.132








Enter Parent Simulation  
Environment icon

Next you will delete unit operations that have no impact on the Dynamic solver.

50. Return to the Main Flowsheet environment by clicking the **Enter Parent Simulation Environment** icon in the toolbar.
51. Close the DePropanizer column property view.  
The ADJ-1 and Dewpoint logical operations have calculated the Cold Gas stream temperature required to achieve a 10°F dewpoint in the SalesGas stream.
52. In the PFD, double-click the ColdGas icon to open the stream property view.

Figure 1.133



53. Record the temperature of the ColdGas material stream so that it may be controlled in Dynamic mode:

When you delete a stream, unit or logical operation from the flowsheet, HYSYS will ask you to confirm the deletion.

Ensure that the **Standard Windows file picker** radio button is selected on the **File** tab in the Session Preferences view. For more information on Session Preferences refer to [Chapter 12.5 - Files Tab](#) in the User Guide.

Variable	Value
<b>Cold Gas Stream Temperature</b>	4.43 F

54. Close the ColdGas property view.
55. On the PFD, click on the ADJ-1 logical operation icon, then press the DELETE key. HYSYS prompts you to confirm that you want to delete the object. Click the **Yes** button.
56. Delete the **Dewpoint** logical operation and the SalesDP material stream from the PFD.
57. From the **File** menu, select **Save As**. Save the file as **DynTUT1-1.hsc**.




## 1.3.2 Column Sizing

In preparation for Dynamic operation, the column and surrounding equipment must be sized. In the steady state environment, column pressure drop is user-specified. In dynamics, it is calculated using dynamic hydraulic calculations. Complications will arise in the transition from steady state to dynamics if the steady state pressure profile across the column is very different from that calculated by the dynamics pressure-flow solver.

### Column Tray Sizing

1. To access the Available Utilities property view, do **one** of the following:
  - Press **CTRL U**.
  - From the **Tools** menu, select **Utilities**.
2. Scroll down the list of available utilities until the Tray Sizing utility is visible.


Figure 1.134






- In the list, select Tray Sizing, then click the **Add Utility** button. The Tray Sizing view appears.

Figure 1.135



- In the **Name** field, change the name to DEPROP TS.
- Click the **Select TS** button. The Select Tray Section view appears.
- In the Flowsheet group, select DePropanizer. In the Object group, select Main TS. Click the **OK** button.


Figure 1.136





7. In the Setup Sections group, click the **Auto Section** button. The Auto Section Information view appears. The default tray internal types appear as follows:

Figure 1.137



**Auto Section Information**

Internal Type  
☐ Sieve ☒ Valve ☐ Bubble Cap ☐ Packed


Area Tolerance  
 When the ratio between the current calc'd area and either of min/max previous areas for the section exceeds this tolerance, a new diameter section is started.  
 Higher more sections; lower fewer sections.

NFP Diam Factor  
 When a new number of flow paths will result in a diameter diff  $\geq$  diam fact \* old diameter, a new NFP section is started.  
 Not required for packed columns.  
 Lower more sections; higher fewer sections.

Cancel Next >

8. Keep the default values; click **Next**. The next view displays the specific dimensions of the valve-type trays.
9. Keep the default values; click the **Complete AutoSection** button.

Figure 1.138



**Tray Section Information**

Internals  
☐ Sieve ☒ Valve ☐ Bubble ☐ Packed

Valve Tray

Orifice Type	Straight
Design Manual	Giltsch
Valve Mat'l Density	513.2 lb/ft <sup>3</sup>
Valve Mat'l Thickness	0.060 in
Hole Area (% of AA)	15.30 %

Common Tray Properties

Tray Spacing	24.00 in
Tray Thickness	0.1250 in
Tray Foaming Factor	1.000
Max Tray dP (ht of liquid)	6.000 in
Max Tray Flooding	85.00 %

DC/Weir Info

Weir Height	2.000 in
Max Weir Loading	120.0 USGPM/R
Downcomer Type	Vertical
Downcomer Clearance	1.500 in
Maximum DC Backup	50.00 %


Delete Complete AutoSection



HYSYS calculates the Main TS tray sizing parameters based on the steady state flow conditions of the column and the desired tray types. HYSYS labels the DePropanizer tray section as Section\_1.

- To confirm the dimensions and configuration of the trays for Section\_1, click the **Performance** tab, then select the **Results** page. Confirm the following tray section parameters for Section\_1, which will be used for the Main TS tray sections.

Figure 1.139



Variable	Value
Section Diameter	2.5 ft
Weir Height	2 in
Tray Spacing	24 in
Total Weir Length	25.38 in

Note the Max DP/Tray value on this page.

You can view column profile information on the Table and Plot pages.

- Click **Design** tab, then select the **Setup** page. Check the **Active** checkbox.
- On the **Results** page of the **Performance** tab, click the **Export Pressures** button. For now, ignore any warnings by clicking the **OK** button.
- Close the Tray Sizing property view and the Available Utilities view.
- Double-click the DePropanizer icon to open the Column property view. Click the **Column Environment** button to enter the Column sub-flowsheet.




15. In the column PFD, double-click the Main TS Column object to open the Main TS property view.
16. Click the **Rating** tab, then select the **Sizing** page.
17. Enter the tray section parameters as follows:

**Be aware that the units for each tray section parameter may not be consistent with the units appearing in the tray sizing utility. Use the drop-down list to select the units you want to input. HYSYS automatically converts the value to the default unit.**

Variable	Value
Section Diameter	2.5 ft
Weir Height	2 in
Tray Spacing	24 in
Total Weir Length	25.38 in


**Figure 1.140**



18. In the Internal Type group, select the **Valve** radio button.



The complete Main TS tray section property view appears below:



19. Close the Main TS property view.
20. Access the Column property view by clicking the **Column Runner** icon.
21. In the **Profiles** page of the **Parameters** tab, note the steady state pressure profile across the column.



Column Runner icon

- The theoretical top and bottom stage pressure should be calculated so that the pressure on stage 5\_Main TS (the Tower Feed stage) is about 203 psia, while the total pressure drop across the column is about 0.7 psi.
22. In the Profiles group, Pressure column, click in the **Pressure** cell for the Condenser and press the DELETE key.
  23. Click in the **Reboiler** pressure cell and press the DELETE key.
  24. Click in the **Pressure** cell for the top stage (1\_Main TS) and input a value of 202.6 psia.
  25. Specify the bottom stage pressure (10\_Main TS) as 203.3 psia.
  26. Click the **Run** button at the bottom of the column property view to start the Column Solver.
  27. Return to the Parent (Main) Simulation environment.
  28. Save the case as **DynTUT1-2.hsc**.



## 1.3.3 Using the Dynamics Assistant

Before you can run the simulation case in Dynamic mode, the degrees of freedom for the flowsheet must be reduced to zero by setting the pressure-flow specifications. It is also necessary to size the existing valves, vessels, coolers, and heat exchangers in the Main Flowsheet and the Column Sub-flowsheet. The following sizing parameters must be specified for these unit operations:

Unit Operation	Sizing Parameter
Valves	Cv value
Vessels	Volume
Coolers/Heat Exchangers	k-values

The Dynamics Assistant makes recommendations as to how the flowsheet topology should change and what pressure-flow specifications are required in order to run a case in Dynamic mode. In addition, it automatically sets the sizing parameters of the equipment in the simulation flowsheet. Not all the suggestions that the Dynamics Assistant offers need to be followed.

The Dynamics Assistant will be used to do the following:

- Add Pressure-Flow specifications to the simulation case.
- Size the Valve, Vessel, and Heat Exchanger operations.






Dynamics Assistant icon

1. Click the **Dynamics Assistant** icon. Browse through each tab in the Dynamics Assistant view to inspect the recommendations.

Figure 1.142




Green checkmarks appear in the Make Changes column beside all recommendations by default. You can choose which recommendations will be executed by the Assistant by activating or deactivating the checkboxes beside each recommendation.

2. Click the **Streams** tab.


The Streams tab contains a list of recommendations regarding the setting or removing of pressure-flow specifications in the flowsheet.

Figure 1.143





If some of the columns or rows on the pages are not visible, use the scroll bars beside or under the information area to bring the columns or rows into view.



An active recommendation will be implemented by the Dynamics Assistant.




An inactive recommendation will be ignored by the Dynamics Assistant.

- For each page in the **Streams** tab, set the following recommendations as active or inactive according to the table shown below:

Tab [Page]	Recommendation	Stream	OK Checkbox
Streams [Pressure Specs]	Remove Pressure Specifications	Feed 1	Active
	Set Pressure Specifications	LiquidProd	Active
		SalesGas	Active
Streams [Flow Specs]	Remove Flow Specifications	Feed 1	Inactive
		Feed 2	Inactive
Streams [Insert Valves]	Insert Valves	Feed 1	Inactive
		Feed 2	Inactive
		Ovhd	Inactive
Streams [Int. Flow Spec]	Set Internal Flow Specification	Reflux	Active

- Click the **Pressure Flow Specs** tab.

Figure 1.144



This tab contains a list of unit operations which can use a Pressure Flow or Pressure Drop (DeltaP) specification. Typically, all unit operations in Dynamic mode should use the Pressure Flow specification.

- Ensure that all the recommendations in this page are active:

Tab [Page]	Recommendation	Unit Operation	OK Checkbox
Pressure Flow Specs [PF versus DP]	Pressure Flow Spec instead of Delta P	Chiller	Active
		Gas/Gas	Active
		Heater	Active




6. Click the **Unknown Sizes** tab.

The Unknown Sizes tab contains a list of the unit operations in the flowsheet that require sizing.

- The Valve operations are sized based on the current flow rate and pressure drop across the valve. The valves are sized with a 50% valve opening.
- The Vessel operation volumes are determined based on the liquid exit volumetric flow rate and a 10-second residence time.
- The Heat Exchanger operations are sized based on the current flow rate and pressure drop across the equipment.

Figure 1.145



You can modify any of the default sizing parameters in the Unknown Sizes tab. Once you modify a sizing parameter, the piece of equipment is automatically sized and the volume, Cv, or k-value displayed.

7. For each page in the **Unknown Sizes** tab, ensure that all the recommendations are active:

Tab [Page]	Recommendation	Unit Operation	OK Checkbox
Unknown Sizes [Volumes]	Vessel Sizing	Chiller	Active
		Gas/Gas (Tube) 1	Active
		Gas/Gas (Shell) 2	Active
Unknown Sizes [k values]	Heat Exchanger Sizing	Chiller	Active
		Gas/Gas (Tube)	Active
		Gas/Gas (Shell)	Active

8. Click the **Tray sections** tab.


The Tray sections tab identifies tray sections and streams whose total steady state pressure drops are inconsistent with the total pressure drop calculated according to the dynamics rating model.

For the purpose of this tutorial, recommendations on this tab will be ignored.



9. Click the **Other** tab.

Figure 1.146



The Other tab contains a list of miscellaneous changes that should be made in order for the Dynamic simulation case to run effectively.

10. Activate the following recommendations:

Tab [Page]	Recommendation	Unit Operation	OK Checkbox
Other [Misc]	Set Equalize Option Mixers	Mixer-101	Active

11. Click the **Make Changes** button *once*. All the active suggestions in the Dynamics Assistant are implemented.
12. Close the Dynamics Assistant view.
13. Switch to Dynamic mode by clicking the **Dynamic mode** icon. When asked “Are you sure you want to switch to dynamics?”, click the **Yes** button.



Dynamic Mode icon

Since you deactivated the suggestion to insert a valve on the Ovhd stream, you must set a pressure-flow specification on this stream.


**You can enter the Ovhd stream pressure specification in either the Main Flowsheet environment or the Column Sub-Flowsheet.**

14. In the PFD, double-click the Ovhd stream icon to open stream property view.
15. Click the **Dynamics** tab, then select the **Specs** page.



16. Activate the **Pressure** specification. The **Pressure** specification should be the only specification active. Ensure that the **Ovhd** Molar Flow specification is inactive.


Figure 1.147



You can specify the exit temperature of the Heater operation in Dynamic mode. The duty of the heater is back-calculated to make the temperature specification.

17. Close the Ovhd property view.
18. In the PFD, double-click the Heater icon to access the property view.
19. Click the **Dynamics** tab, then select the **Specs** page. In the Model Details group, select the **Product Temp Spec** radio button.

Figure 1.148



20. Close the view.
21. Save the case as **DynTUT1-3.hsc**.




## 1.3.4 Adding Controller Operations

In this section you will identify and implement key control loops using PID Controller logical operations. Although these controllers are not required to run in Dynamic mode, they will increase the realism of the model and provide more stability.


PFD of the main flowsheet environment after all controllers are added:

**Figure 1.149**



PFD of the Column sub-flowsheet after controllers are added:

**Figure 1.150**





## Level Control

In this section you will add level controllers to both the Main flowsheet and Column sub-flowsheet to control the liquid levels of each vessel operation.

1. In the Main flowsheet, ensure the Object Palette is open; if it isn't, press F4.
2. In the Object Palette, click the **Control Ops** icon. A sub-palette appears.
3. In the sub-palette, right-click and drag the **PID Controller** icon to the PFD between InletSep and Sep Valve. The controller icon IC-100 appears in the PFD.
4. Double-click the controller icon to open its property view.




Control Ops icon



PID Controller icon

Figure 1.151




5. Click the **Connections** tab. In the **Name** field, change the name of the PID Controller operation to Sep LC.
6. In the Process Variable Source group, click the **Select PV** button. The Select Input PV view appears.




7. In the Object group, select InletSep. In the Variable group, select Liquid Percent Level. Click the OK button.

Figure 1.152



8. In the Output Target Object group, click the **Select OP** button. The Select Op Object view appears.
9. In the Flowsheet group, select Case (Main). In the Object group, select Sep Valve. Click the OK button.

Figure 1.153




10. Click the **Parameters** tab, then select the **Configuration** page.
11. Enter the information specified in the following table:

In this cell...	Enter...
Action	Click the Direct radio button
Kc	2
PV Minimum	0%
PV Maximum	100%



12. Click the **Face Plate** button at the bottom of the property view.
13. Change the controller mode to Auto on the face plate by opening the drop-down list and selecting Auto. Close the face plate view when you are finished.

Figure 1.154



14. Using the same procedures, add another PID Controller operation that will serve as the LTS level controller. Specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	LTS LC
	Process Variable Source	LTS object, Liquid Percent Level variable
	Output Target Object	LTS Valve
<b>Parameters [Configuration]</b>	Action	Direct
	Kc	2
	PV Minimum	0%
	PV Maximum	100%

15. Click the **Face Plate** button. Change the controller mode to Auto on the face plate view.



Object Navigator icon

Next you will enter the Column sub-flowsheet environment.

16. Instead of entering through the Column property view, click the **Object Navigator** icon in the Toolbar.
17. Double-click on DePropanizer in the Flowsheets group to enter the Column sub-flowsheet environment.
18. Ensure the PFD for the column is visible.



The Column sub-flowsheet uses a simplified Object Palette.

To add a PID Controller operation in the sub-flowsheet, right-click the PID Controller icon in the Object Palette and drag the cursor to the PFD.

19. In the Column sub-flowsheet, add a PID Controller operation that will serve as the Condenser level controller. Specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	Cond LC
	Process Variable Source	Condenser, Liquid Percent Level
	Output Target Object	Reflux
<b>Parameters [Configuration]</b>	Action	Direct
	Kc	1
	Ti	5 minutes
	PV Minimum	0%
	PV Maximum	100%

20. Click the **Control Valve** button. The FCV for Reflux view appears.

21. Enter the following details in the Valve Sizing group:

In this cell...	Enter...
<b>Flow Type</b>	Molar Flow
<b>Minimum Flow</b>	0 lbmole/h
<b>Maximum Flow</b>	500 lbmole/h

The Flow values shown here do not use the default units. Enter the values, then select the correct units from the drop-down list. HYSYS automatically converts the values to the default units.

22. Close the FCV for Reflux view.
23. Click the **Face Plate** button. Change the controller mode to Auto on the face plate view, then close the view.
24. Close the Cond LC controller view.
25. Add another PID Controller operation that will serve as the Reboiler level controller. Specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	Reb LC
	Process Variable Source	Reboiler, Liq Percent Level
	Output Target Object	RebDuty
<b>Parameters [Configuration]</b>	Action	Direct
	Kc	0.1
	Ti	3 minutes
	PV Minimum	0%
	PV Maximum	100%



The values shown here do not use the default units. Enter the values, then select the correct units from the drop-down list. HYSYS automatically converts the values to the default units.

26. Click the **Control Valve** button. The FVC for RebDuty view appears.
27. In the Duty Source group, select the **Direct Q** radio if it is not already selected.
28. In the Direct Q group, enter the following values:

In this cell...	Enter...
<b>Min Available</b>	0 Btu/h
<b>Max Available</b>	$6 \times 10^6$ Btu/h

29. Close the FCV for RebDuty view.
30. Click the **Face Plate** button. Change the controller mode to Auto on the face plate. Close the face plate view.
31. Close the Reb LC property view.

## Temperature Control

Temperature control is important in this dynamic simulation case. A temperature controller will be placed on the ColdGas stream to ensure that the SalesGas stream makes the 10°F dewpoint specification. Temperature control will be placed on the top and bottom stages of the depropanizer to ensure product quality and stable column operation.

1. Enter the Main Flowsheet environment by clicking the **Enter Parent Simulation Environment** button.



Enter Parent Simulation Environment icon

Next you will add a PID Controller operation that will serve as the ColdGas temperature controller.

2. On the Object Palette, click the **Control Ops** icon. A sub-palette appears.
3. Right-click the **PID Controller** icon, and drag the cursor to the PFD.
4. Double-click the controller icon to open its property view. Specify the following details:



Control Ops icon



PID Controller icon

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	Cold TC
	Process Variable Source	ColdGas, Temperature
	Output Target Object	C3Duty



The temperature values shown here do not use the default units. Enter the values, then select the correct units from the drop-down list. HYSYS automatically converts the values to the default units.

Tab [Page]	In this cell...	Enter...
<b>Parameters [Configuration]</b>	Action	Direct
	Kc	1
	Ti	10 minutes
	PV Minimum	-20 °F
	PV Maximum	20 °F

5. Click the **Control Valve** button. The FCV for C3Duty appears.
6. In the Duty Source group, select the **Direct Q** radio button.
7. In the Direct Q group, enter the following details:

In this cell...	Enter...
<b>Min Available</b>	0 Btu/h
<b>Max Available</b>	$2 \times 10^6$ Btu/h

The values shown here do not use the default units. Enter the values, then select the correct units from the drop-down list. HYSYS automatically converts the values to the default units.

8. Close the FCV for C3Duty view.
9. Click the **Face Plate** button. Change the controller mode to Auto on the face plate view, then close the view.
10. Enter the Depropanizer Column sub-flowsheet environment.
11. Add a PID Controller operation that will serve as the Depropanizer Top Stage temperature controller.
12. In the controller property view, specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	Top Stage TC
	Process Variable Source	Main TS, Top Stage Temperature
	Output Target Object	CondDuty
<b>Parameters [Configuration]</b>	Action	Direct
	Kc	1
	Ti	5 minutes
	PV Minimum	50 °F
	PV Maximum	130 °F

Ensure that you select the correct temperature units from the units drop-down list.

13. Click the **Control Valve** button. The FCV for CondDuty view appears.
14. In the Duty Source group, select the **Direct Q** radio button.



Ensure that you select the correct units from the units drop-down list.

15. in the Direct Q group, enter the following details:

In this cell...	Enter...
Min Available	0 Btu/h
Max Available	$3 \times 10^6$ Btu/hr

16. Close the FCV for CondDuty view.
17. Click the **Face Plate** button. The Top Stage TC view appears.
18. Change the controller mode to Auto. In the **PV** field, enter a set point of 86 °F. HYSYS automatically converts this value to °C.
19. Close the Top Stage TC face plate view.
20. Close the Top Stage TC property view.
21. Add another PID Controller operation that will serve as the Depropanizer 9th stage temperature controller.
22. In the controller property view, specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	Stage9 TC
	Process Variable Source	Main TS, Stage Temperature, 9_Main TS
	Output Target Object	Reboil Valve
<b>Parameters [Configuration]</b>	Action	Direct
	Kc	2
	Ti	5 minutes
	PV Minimum	110 °F
	PV Maximum	260 °F

Ensure that you select the correct temperature units from the units drop-down list.

23. Click the **Face Plate** button. The Stage 9 TC face plate view appears.
24. Change the controller mode to Auto. In the **PV** field, input a set point of 184 °F.

You should be able to run the integrator at this point without any problems, however, you will probably want to monitor important variables in the dynamic simulation using strip charts.

25. Return to the Parent Environment.
26. Save the case as **DynTUT1-4.hsc**.




## Monitoring in Dynamics

Now that the model is ready to run in Dynamic mode, you will create a strip chart to monitor the general trends of key variables. The following is a general procedure for installing strip charts in HYSYS.

1. Open the Databook by using the hot key combination CTRL D.

Figure 1.155




For more information, refer to [Using the Databook](#) on page 78.

In the next set of steps, you will add all of the variables that you would like to manipulate or model.

- Include feed and energy streams that you want to modify in the dynamic simulation.
  - Include unit operation temperature, levels and pressures that you want to monitor and record.
2. On the **Variables** tab, click the **Insert** button. The Variable Navigator appears.

Figure 1.156





Select Case (Main) in the Flowsheet group to ensure you can find all streams and operations.

The purpose of selecting manipulated and monitored objects is to see how the monitored objects will respond to the changes you make to the manipulated variable.

To make the strip chart easier to read, do not activate more than six variables per strip chart.


To change the configuration of each strip chart, click the **Setup** button.

3. Select the Flowsheet, Object and Variable groups for any of the following suggested variables.

Variables to Manipulate	Variables to Monitor
Tower Feed, Molar Flow	Ovhd, Molar Flow
Heater Q, Utility Outlet Temperature	LiquidProd, Molar Flow
Feed 1, Molar Flow	InletSep, Liquid Percent Level
Feed 2, Molar Flow	LTS, Liquid Percent Level

4. Click the **Add** button to add the selected variable to the **Variables** page.
5. Repeat steps #3 and #4 to add any remaining variables to the Databook.
6. Click the **Strip Charts** tab.
7. In the Available Strip Charts group, click the **Add** button. HYSYS will create a new strip chart with the default name DataLogger1. You may change the default name by editing the Logger Name cell.
8. In the table, check the **Active** checkbox for each of the variables that you would like to monitor on this particular strip chart.

Figure 1.157



9. If required, add more strip charts by repeating steps #7 and #8.
10. To access a strip chart view, select the strip chart name, then click the **Strip Chart** button.
11. Minimize the Databook view.
12. Before starting the integrator, open the property view for the Ovhd stream in the Column sub-flowsheet.
13. Click the **Dynamics** tab, then select the **Specs** page.





Start Integrator icon (green)

14. In the Dynamic Specifications group, ensure that the Pressure specification checkbox is **Active** and the Molar Flow specification checkbox is **Inactive**.
15. Close the Ovhd stream view.
16. Arrange both strip chart views so you can see them.
17. Start the Integrator by clicking the **Start Integrator** icon in the tool bar and observe as the variables line out on the strip charts.
18. Click the **Stop Integrator** icon to stop the process.
19. To use the Databook feature for analysis, manipulate the stream and operation variables via their property views, click the **Start Integrator** icon again, and view the results in the monitored variables in the strip charts.







# 2 Refining Tutorial

<b>2.1 Introduction .....</b>	<b>3</b>
<b>2.2 Steady State Simulation .....</b>	<b>5</b>
2.2.1 Process Description .....	5
2.2.2 Setting Your Session Preferences .....	7
2.2.3 Building the Simulation .....	10
2.2.4 Entering the Simulation Environment .....	37
2.2.5 Using the Workbook .....	39
2.2.6 Installing Unit Operations .....	47
2.2.7 Using Workbook Features .....	52
2.2.8 Using the PFD .....	56
2.2.9 Viewing and Analyzing Results .....	97
2.2.10 Installing a Boiling Point Curves Utility .....	99
2.2.11 Using the Databook .....	104
<b>2.3 Dynamic Simulation .....</b>	<b>114</b>
2.3.1 Simplifying the Steady State Flowsheet .....	115
2.3.2 Adding Equipment & Sizing Columns .....	119
2.3.3 Adding Controller Operations .....	130
2.3.4 Adding Pressure-Flow Specifications .....	136
2.3.5 Monitoring in Dynamics .....	142







## 2.1 Introduction


You will build the Refining simulation using the following basic steps:

1. Create a unit set.
2. Choose a property package.
3. Select the non-oil components.
4. Characterize the Oil.
5. Create and specify the preheated crude and utility steam streams.
6. Install and define the unit operations in the pre-fractionation train.
7. Install and define the crude fractionation column.

This complete case has also been pre-built and is located in the file **TUTOR2.HSC** in your HYSYS\Samples directory.

In this tutorial, crude oil is processed in a fractionation facility to produce naphtha, kerosene, diesel, atmospheric gas oil, and atmospheric residue products. Preheated crude (from an upstream preheat train) is fed to a pre-flash drum where vapours are separated from the liquids, which are heated in a furnace. The pre-flash vapours bypass the furnace and are recombined with the hot crude from the furnace. The combined stream is then fed to the atmospheric crude column for fractionation. The main flowsheet for this process appears below.


Figure 2.1





The crude column consists of a refluxed absorber with three side strippers and three cooled pump around circuits. The column sub-flowsheet appears below.

**Figure 2.2**



The following pages guide you through building a HYSYS case for modeling this process. This tutorial illustrates the complete construction of the simulation, from selecting a property package and components, characterizing the crude oil, to installing streams and unit operations, through to examining the final results. The tools available in HYSYS are utilized to illustrate the flexibility available to you.

**Before proceeding, you should have read [Chapter A - HYSYS Tutorials](#) which precedes the Tutorials in this manual.**




## 2.2 Steady State Simulation

### 2.2.1 Process Description

This example models a crude oil processing facility consisting of a pre-fractionation train used to heat the crude liquids, and an atmospheric crude column to fractionate the crude into its straight run products. The Main Flowsheet for this process appears in the following figure.

Figure 2.3




Preheated crude (from a preheat train) is fed to the pre-flash drum, modeled as a Separator, where vapours are separated from the crude liquids. The liquids are then heated to 650°F in the crude furnace, modeled as a Heater. The pre-flash vapours bypass the furnace and are re-combined, using a Mixer, with the hot crude stream. The combined stream is then fed to the atmospheric crude column for separation.



The crude column is modeled as a Refluxed Absorber, equipped with three pump-around and three side-stripper operations. The Column sub-flowsheet appears in the figure below.

Figure 2.4



The main column consists of 29 trays plus a partial condenser. The TowerFeed enters on stage 28, while superheated steam is fed to the bottom stage. In addition, the trim duty is represented by an energy stream feeding onto stage 28. The Naphtha product, as well as the water stream WasteH2O, are produced from the three-phase condenser. Crude atmospheric Residue is yielded from the bottom of the tower.

Each of the three-stage side strippers yields a straight run product. Kerosene is produced from the reboiled KeroSS side stripper, while Diesel and AGO (atmospheric gas oil) are produced from the steam-stripped DieselSS and AGOSS side strippers, respectively.

The Workbook displays information about streams and unit operations in a tabular format, while the PFD is a graphical representation of the flowsheet.

The two primary building tools, Workbook and PFD, are used to install the streams and operations and to examine the results while progressing through the simulation. Both of these tools provide you with a large amount of flexibility in building your simulation, and in quickly accessing the information you need.




The Workbook is used to build the first part of the flowsheet, from specifying the feed conditions through to installing the pre-flash separator. The PFD is then used to install the remaining operations, from the crude furnace through to the column.

## 2.2.2 Setting Your Session Preferences

1. Start HYSYS and create a new case. The Simulation Basis Manager view appears.

Figure 2.5



The default Preference file is named **HYSYS.prf**. When you modify any of the preferences, you can save the changes in a new Preference file by clicking the **Save Preference Set** button. HYSYS prompts you to provide a name for the new Preference file, which you can later use in any simulation case by clicking the **Load Preference Set** button.

Your first task is to set your Session Preferences.


2. From the **Tools** menu, select **Preferences**. The Session Preferences view appears.

The most important preference you will set is the unit set. HYSYS does not allow you to change any of the default unit sets listed, however, you can create a new unit set by cloning an existing one. In this tutorial you will create a new unit set based on the HYSYS Field set and customized it.



3. Click the **Variables** tab, then select the **Units** page.
4. In the Available Unit Sets group, select Field.

Figure 2.6




5. Click the **Clone** button. A new unit set named NewUser appears and is automatically selected as the current unit set.
6. In the **Unit Set Name** field, rename the new unit set to Field-density. You can now change the units for any variable associated with this new unit set.
7. In the Display Units group, use the vertical scroll bar to find the **Standard Density** cell.  
The current default unit for Standard Density is lb/ft3. A more appropriate unit for this example is API\_60.
8. Click in the **Standard Density** cell on lb/ft3.
9. Press SPACEBAR or click the down arrow to open the drop-down list of available units.




10. In the unit list, select API\_60.

Figure 2.7



11. Repeat steps #8-#10 to change the Mass Density units to API.

Figure 2.8



All commands accessed via the toolbar are also available as Menu items.

12. Your new unit set is now defined. Close the Session Preference view to return to the Simulation Basis Manager view.




## 2.2.3 Building the Simulation

### Selecting Components

Before defining a fluid package in HYSYS, you will create a component list for the fluid package. In this example, the component list contains non-oil components, Light Ends and hypocomponents. You must first add the non-oil components and Light Ends from HYSYS pure component library into the component list.

1. Click the **Components** tab, then click the **Add** button. The Component List View view appears.

Figure 2.9



There are a number of ways to select components for your simulation. One method is to use the matching feature. Notice that each component is listed in three ways on the Selected tab:

Matching Method	Description
<b>SimName</b>	The name appearing within the simulation.
<b>FullName/Synonym</b>	IUPAC name (or similar), and synonyms for many components.
<b>Formula</b>	The chemical formula of the component. This is useful when you are unsure of the library name of a component, but know its formula.



The Component List View contains two tabs. In this example, the Selected tab is the only tab used, because it contains all the functions you need to add components to the list.

You can also move to the Match field by pressing **ALT M**.

At the top of each of these three columns is a corresponding radio button. Based on the selected radio button, HYSYS will locate the component(s) that best matches the input you type in the **Match** cell.


- Optional: To rename the component list, click in the **Name** field at the bottom of the view and type a new name.

For this tutorial example, you will add the following non-oil components: H<sub>2</sub>O, C<sub>3</sub>, iC<sub>4</sub>, nC<sub>4</sub>, iC<sub>5</sub> and nC<sub>5</sub>.

First, you will add H<sub>2</sub>O using the match feature.

- Ensure the **Sim Name** radio button is selected, and the **Show Synonyms** checkbox is checked.
- Click in the **Match** field.
- Begin typing 'water'. HYSYS filters through its library as you type, displaying only those components that match your input.

**Figure 2.10**




- With Water selected, add it to the Current Component List by doing **one** of the following:
  - Press the **ENTER** key.
  - Click the **Add Pure** button.
  - Double-click on Water.




You can also use the Family Filter to display only those components belonging to certain families. Next, you will add Propane to the component list using a Family Filter:

7. Ensure the **Match** field is empty, and click the **View Filter** button. The Filters view appears as shown on the left.
8. On the Filters view, check the **Use Filter** checkbox to activate the Family Filter.
9. Check the **Hydrocarbons** checkbox. The remaining components are known to be hydrocarbons.



Filters view

Figure 2.11



The Match feature remains active when you are using a family filter, so you could have also typed **C3** in the Match field and then added it to the component list.

10. Double-click Propane to add it to the component list.



Next you will add the remaining Light Ends components iC4 through nC5. The following procedure shows you quick way to add components that appear consecutively in the library list.

11. Click on the first component to be added (in this case, iC4).


12. Do **one** of the following:

- Hold down the **SHIFT** key and click on the last component, in this case nC5. All components iC4 through nC5 are now selected. Release the **SHIFT** key.
- Click and drag from iC4 to nC5. Components iC4 through to nC5 are selected.

13. Click the **Add Pure** button. The selected components are transferred to the Selected Component group.

To select consecutive components, use the **SHIFT** key. To select non-consecutive components, use the **CTRL** key.

Figure 2.12



The complete list of non-oil components appears in the figure above.

14. Close the Component List View and Filters views to return to the Simulation Basis Manager view.

On the Components tab, the Component Lists group now contains the name of the new component list that you created.



The Simulation Basis Manager allows you to create, modify, and otherwise manipulate fluid packages in your simulation case. Most of the time, as with this example, you require only one fluid package for your entire simulation.

HYSYS displays the current Environment and Mode in the upper right corner of the view. Whenever you begin a new case, you are automatically placed in the Basis environment, where you can choose the property package and non-oil components.

HYSYS has created a fluid package with the default name Basis-1. You can change the name of this fluid package by typing a new name in the **Name** field at the bottom of the view.

## Defining a Fluid Package


In the Simulation Basis Manager view, your next task is to define a fluid package.

A fluid package contains the components and property method HYSYS will use in its calculations for a particular flowsheet. Depending on what is required, a fluid package can also contain other information, such as a petroleum fluid characterization.

The fluid package for this example will contain the property package (Peng Robinson), the pure components H<sub>2</sub>O, C<sub>3</sub>, iC<sub>4</sub>, nC<sub>4</sub>, iC<sub>5</sub>, nC<sub>5</sub>, and the hypothetical components which are generated in the Oil characterization.

1. Click the **Fluid Pkgs** tab, then click the **Add** button. The Fluid Package: Basis-1 view appears.

Figure 2.13



This view is divided into a number of tabs that allow you to supply all the information necessary to completely define the fluid package. For this tutorial, however, only the Set Up tab is used.


On the Set Up tab, the currently selected Property Package is <none>. Before you begin characterizing your petroleum fluid, you must choose a property package that can handle hypothetical components.



2. Select the Peng Robinson property package by doing **one** of the following:
  - Type 'Peng Robinson'. HYSYS finds the match to your input.
  - Use the up and down arrow keys to scroll through the list of available property packages until Peng Robinson is selected.
  - Use the vertical scroll bar to scroll through the list until Peng Robinson becomes visible, then click on it.

The Fluid Package: Basis - 1 view appears as shown below.

**Figure 2.14**



The Property Pkg indicator now indicates **Peng Robinson** is the current property package for this fluid package.

Alternatively, you could have selected the EOSs radio button in the Property Pkg Filter group. The list would then display only those property packages that are Equations of State. Peng Robinson would appear in this filtered list.

In the Component List Selection group, you could use the drop-down list to find the name of any component lists you had created (currently empty). The View button opens the Component List View view of the selected component list.


If you have multiple fluid packages and components lists in a case, you can use the drop-down list in the Component List Selection group to attach a component list to a particular property package.

**If the selected component list contains components not appropriate for the selected property package, HYSYS opens the Components Incompatible with Property Package view. On this view, you have the options of HYSYS removing the incompatible components from the component list or changing to a different property package using the drop-down list or the Cancel button.**



3. Close the Fluid Package: Basis - 1 view to return to the Simulation Basis Manager view.

Figure 2.15



The list in the Current Fluid Packages group displays the new fluid package, Basis-1, showing the number of components (NC) and property package (PP). The new fluid package is assigned by default to the main flowsheet, as shown in the Flowsheet-Fluid Pkg Associations group.

## Creating Hypocomponents

Your next task is to create and add the hypocomponents to the component list. In this example, you will characterize the oil (Petroleum Fluid) using the given Assay data to create the hypocomponents.



## Characterizing the Oil

In this section, you will use the following laboratory Assay data:

Bulk Crude Properties	
MW	300.00
API Gravity	48.75

Light Ends Liquid Volume Percent	
i-Butane	0.19
n-Butane	0.11
i-Pentane	0.37
n-Pentane	0.46

TBP Distillation Assay		
Liquid Volume Percent Distilled	Temperature (°F)	Molecular Weight
0.0	80.0	68.0
10.0	255.0	119.0
20.0	349.0	150.0
30.0	430.0	182.0
40.0	527.0	225.0
50.0	635.0	282.0
60.0	751.0	350.0
70.0	915.0	456.0
80.0	1095.0	585.0
90.0	1277.0	713.0
98.0	1410.0	838.0

API Gravity Assay	
Liq Vol% Distilled	API Gravity
13.0	63.28
33.0	54.86
57.0	45.91
74.0	38.21
91.0	26.01




Viscosity Assay		
Liquid Volume Percent Distilled	Viscosity (cP) 100°F	Viscosity (cP) 210°F
10.0	0.20	0.10
30.0	0.75	0.30
50.0	4.20	0.80
70.0	39.00	7.50
90.0	600.00	122.30

## Accessing the Oil Environment

The HYSYS Oil Characterization procedure is used to convert the laboratory data into petroleum hypocomponents.

1. On the Simulation Basis Manager view, click the **Oil Manager** tab.

Figure 2.16



The Associated Fluid Package drop-down list indicates which fluid package is used for the oil characterization. Since there is only one fluid package, HYSYS has made **Basis-1** the Associated Fluid Package.

The text on the right side of the view indicates that before entering the Oil Environment, two criteria must be met:

- at least one fluid package must be present. In this case, only one fluid package, Basis-1, is selected.
- the property package must be able to handle Hypothetical Components. In our case, the property package is Peng Robinson, which is capable of handling Hypothetical components.





Oil Environment icon


The Oil Characterization view allows you to create, modify, and otherwise manipulate the Assays and Blends in your simulation case. For this example, the oil is characterized using a single Assay.

Since both criteria are satisfied, the oil is characterized in the Oil Environment.

2. To enter the Oil Characterization environment, do **one** of the following:
  - click the **Enter Oil Environment** button on the Oil Manager tab.
  - click the **Oil Environment** icon on the toolbar.

The Oil Characterization view appears.

Figure 2.17



In general, three steps must be completed when you are characterizing a petroleum fluid:

1. Supply data to define the Assay.
2. Cut the Assay into hypothetical components by creating a Blend.
3. Install the hypothetical components into the fluid package.




## Defining the Assay

1. On the **Assay** tab, click the **Add** button to create and view a new Assay. The Assay view appears.

HYSYS has given the new Assay the default name of Assay-1. You can change this by typing a new name in the **Name** field.

Figure 2.18



When the property view for a new Assay is opened for the first time, the view contains minimal information. Depending on the Assay Data Type you choose, the view is modified appropriately. For this example, the Assay is defined based on TBP data.



- From the Assay Data Type drop-down list, select TBP. The view is customized for TBP data.

Figure 2.19


The screenshot shows the 'Assay: Assay-1' dialog box. The 'Assay Definition' section on the left contains several drop-down menus: 'Bulk Properties' (Not Used), 'Assay Data Type' (TBP), 'Light Ends' (Ignore), 'Molecular Wt. Curve' (Not Used), 'Density Curve' (Not Used), and 'Viscosity Curves' (Not Used). Below these is a 'TBP Distillation Conditions' section with 'Atmospheric' selected and 'Vacuum' unselected. A 'Light Ends Handling & Bulk Fitting Options' button is at the bottom of this section. The 'Input Data' section on the right shows 'Assay Basis' set to 'Mole'. Below this is a table with two columns: 'Assay Percent' and 'Temperature [C]'. The table has 10 rows, all of which are empty. A yellow message bar at the bottom of the table states 'At least 5 points are required'. At the bottom of the dialog, there are tabs for 'Input Data', 'Calculation Defaults', 'Working Curves', 'Plots', 'Correlations', 'User Curves', and 'Notes'. The 'Input Data' tab is active. Below the tabs, there is a 'Delete' button, a 'Name:' field with 'Assay-1', a yellow message bar stating 'Assay Was Not Calculated', and a 'Calculate' button.

The next task is to enter the composition of the Light Ends in the Assay.

- From the Light Ends drop-down list, select Input Composition.
- In the Input Data group, select the **Light Ends** radio button.
- Ensure that Liquid Volume% is selected in the Light Ends Basis drop-down list.
- Click in the **Composition** cell for i-Butane.
- Type 0.19, then press the ENTER key. You are automatically advanced down one cell to n-Butane.



- Figure 2.20**



9. From the Bulk Properties drop-down list, select Used. A new radio button labeled Bulk Props appears in the Input Data group.
10. From Molecular Wt. Curve drop-down list, select Dependent. A new radio button labeled **Molecular Wt** appears in the Input Data group.
11. From the Density Curve and Viscosity Curves drop-down lists, select Independent as the curve type. For Viscosity, two radio buttons appear as HYSYS allows you to input viscosity assay data at two temperatures.

Input Data

- ☐ Bulk Props
- ☒ Light Ends
- ☐ Distillation
- ☐ Molecular Wt
- ☐ Density
- ☐ Viscosity1
- ☐ Viscosity2



In the next few sections, you will enter the following laboratory assay data:

- bulk molecular weight and density
- TBP Distillation assay data
- dependent molecular weight assay data
- independent density assay data
- independent viscosity assay data (at two temperatures)

### Entering Bulk Property Data

1. Select the **Bulk Props** radio button, and the bulk property table appears to the right of the radio buttons.
2. Click in the Molecular Weight cell in the table. Type 300 and press ENTER. You are automatically advanced down one cell to the **Standard Density** cell.
3. In the Standard Density cell, enter 48.75 and press SPACE BAR. To the right of the cell, a field containing the current default unit associated with the cell appears. When you defined the new unit set, you specified the default unit for standard density as API\_60, which appears in the field.

Figure 2.21

The screenshot shows the 'Assay: Assay-1' window. On the left, under 'Assay Definition', the following options are selected: Bulk Properties (Used), Assay Data Type (TBP), Light Ends (Input Composition), Molecular Wt. Curve (Dependent), Density Curve (Independent), and Viscosity Curves (Independent). Under 'TBP Distillation Conditions', 'Atmospheric' is selected. On the right, the 'Input Data' table is displayed with the following values:

Molecular Weight	300.0
Standard Density	48.75 API_60
Watson UOPK	<empty>
Viscosity Type	Dynamic
Viscosity 1 Temp	100.0 F
Viscosity 1	<empty>
Viscosity 2 Temp	210.0 F
Viscosity 2	<empty>

At the bottom, the 'Input Data' tab is active. The 'Name' field contains 'Assay-1'. A yellow status bar displays the message 'Assay Was Not Calculated'. The 'Calculate' button is visible on the right.

4. Since this is the correct unit, press ENTER, and HYSYS accepts the density value.



No bulk Watson UOPK or Viscosity data is available for this assay. HYSYS provides two default temperatures (100°F and 210°F) for entering bulk viscosity, but these temperature values are ignored unless corresponding viscosities are provided. Since the value for bulk viscosity is not supplied, there is no need to delete or change the temperature values.

### Entering Boiling Temperature [TBP] Data

The next task is to enter the TBP distillation data.

1. Click the **Calculation Defaults** tab.
2. In the Extrapolation Methods group, select Lagrange from the Distillation drop-down list.
3. Return to the **Input Data** tab.
4. Select the **Distillation** radio button. The corresponding TBP data matrix appears. HYSYS displays a message under the matrix, stating that 'At least 5 points are required' before the assay can be calculated.
5. From the Assay Basis drop-down list, select Liquid Volume.
6. Click the **Edit Assay** button. The Assay Input Table view appears.
7. Click in the top cell of the Assay Percent column.
8. Type 0, then press the ENTER key. You are automatically advanced to the corresponding empty Temperature cell.
9. Type 80 then press the ENTER key. You are automatically advanced down to the next empty Assay Percent cell.



10. Repeat steps #8 and #9 to enter the remaining Assay Percent and Temperature values as shown.

Figure 2.22

Assay Percent [%]	Temperature [F]
0.0000	80.00
10.00	255.0
20.00	349.0
30.00	430.0
40.00	527.0
50.00	635.0
60.00	751.0
70.00	915.0
80.00	1095
90.00	1277
98.00	1410
<empty>	<empty>

All input curves except distillation are on midpoint basis. Dependent curves will be shifted to middle.

Cancel OK

11. Click the **OK** button to return to the Assay property view.

### Entering Molecular Weight Data

1. Select the **Molecular Wt** radio button. The corresponding assay matrix appears. Since the Molecular Weight assay is Dependent, the Assay Percent column displays the same values as those you entered for the Boiling Temperature assay. Therefore, you need only enter the Molecular Weight value for each assay percent.
1. Click the **Edit Assay** button and the Assay Input Table view appears.
2. Click on the first empty cell in the Mole Wt column.
3. Type 68, then press the down arrow key.



4. Type the remaining Molecular Weight values as shown.

Figure 2.23

Assay Percent [%]	Mole Wt.
0.0000	68.00
10.00	119.0
20.00	150.0
30.00	182.0
40.00	225.0
50.00	282.0
60.00	350.0
70.00	456.0
80.00	585.0
90.00	713.0
98.00	838.0

All input curves except distillation are on midpoint basis. Dependent curves will be shifted to middle.

Cancel OK

5. Click the OK button when you are finished.

### Entering Density Data

1. Select the **Density** radio button. The corresponding assay matrix appears. Since the Density assay is Independent, you must input values in both the **Assay Percent** and **Density** cells.
2. Using the same method as for the previous assays, enter the API gravity curve data as shown here.

Figure 2.24

Assay Percent [%]	Mass Density [API]
13.00	63.28
33.00	54.86
57.00	45.91
74.00	38.21
91.00	26.01
<empty>	<empty>

All input curves except distillation are on midpoint basis. Dependent curves will be shifted to middle.

Cancel OK



## Entering Viscosity Data

1. Select the **Viscosity 1** radio button. The corresponding assay matrix appears.
2. In the Viscosity Type drop-down list above the assay matrix, ensure Dynamic is selected.
3. In the Viscosity Curves group, select the **Use Both** radio button. The Temperature field is for each of the two viscosity curves.
4. Input the Viscosity 1 assay data as shown here. This viscosity curve corresponds to Temperature 1, 100°F.

Click the **Edit Assay** button to access the Assay Input Table.

**Figure 2.25**

Input Data

☐ Bulk Props  
☐ Light Ends  
☐ Distillation  
☐ Molecular Wt  
☐ Density  
☒ Viscosity1  
☐ Viscosity2

Viscosity Type: **Dynamic**

Temperature: **100.0 F**

Assay Percent	Viscosity-1 [cP]
10.00	0.2000
30.00	0.7500
50.00	4.200
70.00	39.00
90.00	600.0

Viscosity Curves

☐ Use Curve 1  
☐ Use Curve 2  
☒ Use Both

**Edit Assay...**

**Table is Ready**

5. Select the **Viscosity 2** radio button.
6. Enter the assay data corresponding to Temperature 2, 210°F, as shown.

**Figure 2.26**

Assay Percent [%]	Viscosity [cP]
10.00	0.1000
30.00	0.3000
50.00	0.8000
70.00	7.500
90.00	122.3
<empty>	<empty>
<empty>	<empty>


The Assay is now completely defined based on our available data.

7. Click the **Calculate** button at the bottom of the Assay view. HYSYS calculates the Assay, and the status message at the bottom of the view changes to Assay Was Calculated.



8. Click the **Working Curves** tab of the Assay property view to view the calculated results.

Figure 2.27



HYSYS has calculated 50 points for each of the Assay Working Curves.

To view the Assay data you input in a graphical format, click the **Plots** tab. The input curve that appears is dependent on the current variable in the Property drop-down list. By default, HYSYS plots the Distillation (TBP) data. This plot appears below.


The plot view can be re-sized to make the plot more readable. To re-size the view, do **one** of the following:

- Click and drag the outside border to the new size.
- Click the **Maximize** icon.



Maximize icon

Figure 2.28





The independent (x-axis) variable is the Assay percent, while the dependent variable is the TBP in °F. You can view any of the other input curves by selecting the appropriate variable in the Property drop-down list.

The remaining tabs in the Assay property view provide access to information which is not required for this tutorial.


9. Close the Assay view to return to the Oil Characterization view.

## Cutting the Assay (Creating the Blend)

Now that the assay has been calculated, the next task is to cut the assay into individual petroleum hypoccomponents.

1. Click the **Cut/Blend** tab of the Oil Characterization view.
2. Click the **Add** button. HYSYS creates a new Blend and displays its property view.

Figure 2.29



3. In the list of Available Assays, select Assay-1.



4. Click the **Add** button. There are two results:
  - The Assay is transferred to the Oil Flow Information table. (When you have only one Assay, there is no need to enter a Flow Rate in this table.)
  - A Blend (Cut) is automatically calculated based on the current Cut Option.


In this case, the Blend was calculated based on **Auto Cut**, the default Cut Option. HYSYS calculated the Blend based on the following default values for the boiling point ranges and number of cuts per range:

- IBP to 800°F: 25°F per cut, generating  $[(800-\text{IBP})/25]$  hypoccomponents
- 800 to 1200°F: 50°F per cut, generating 8 hypoccomponents
- 1200 to 1400°F: 100°F per cut, generating 2 hypoccomponents

The IBP, or initial boiling point, is the starting point for the first temperature range. The IBP is the normal boiling point (NBP) of the heaviest component in the Light Ends, in this case n-Pentane at 96.9°F. The first range results in the generation of  $(800-96.9)/25 = 28$  hypoccomponents. All the cut ranges together result in a total of  $28+8+2 = 38$  hypoccomponents.

5. Click the **Tables** tab to view the calculated properties of these hypoccomponents.

Figure 2.30





Since the NBP of the heaviest Light Ends component is the starting point for the cut ranges, these hypocomponents were generated on a "light-ends-free" basis. That is, the Light Ends are calculated separately and are not included in these hypocomponents.

These components could be used in the simulation. Suppose, however, that you do not want to use the IBP as the starting point for the first temperature range. You could specify another starting point by changing the Cut Option to **User Ranges**. For illustration purposes, 100°F is used as the initial cut point.

6. Return to the **Data** tab.
7. From the Cut Option Selection drop-down list, select User Ranges. The Ranges Selection group appears.
8. In the **Starting Cut Point** field, enter 100°F. This is the starting point for the first range. The same values as the HYSYS defaults are used for the other temperature ranges.
9. In the Cut End point T column in the table, click on the top cell labeled **<empty>**. The value you will enter in this cell is the upper cut point temperature for the first range (and the lower cut point for the second range).
10. Type 800, then press the down arrow key.
11. Enter the remaining cut point temperatures and the Num. of Cuts values as shown in the figure below.

**Figure 2.31**

Cut End point T (F)	Num. of Cuts
800.000	28
1200.000	8
1400.000	2
<empty>	

12. Once you have entered the data, click the **Submit** button to calculate the Blend based on the current initial cut point and range values. The message Blend Was Calculated appears in the status bar.



HYSYS has provided the Initial Boiling Point (IBP) and Final Boiling Point (FBP). The IBP is the normal boiling point (NBP) of the heaviest component in the Light Ends (in this case, n-Pentane). The FBP is calculated by extrapolating the TBP Assay data to 100% distilled.

- Click the **Tables** tab to view the properties of the petroleum hypoccomponents.

Figure 2.32

Blend: Blend-1

Table Type: Component Properties

Table Control: Main Properties

Oil: Blend-1

Component Physical Properties

Comp Name	NBP [F]	Mole Wt.	Density [API]	Viscosity1 [cP]	Viscosity2 [cP]
NBP_113	113.2	82.49	92.50	0.12818	6.0146e-00
NBP_139	138.6	91.03	90.73	0.13379	6.3480e-00
NBP_164	163.6	107.7	85.18	0.14154	6.8016e-00
NBP_188	187.6	124.1	80.71	0.15184	7.3929e-00
NBP_213	212.8	138.4	76.48	0.16473	8.1156e-00
NBP_238	238.2	145.5	72.42	0.18107	9.0047e-00
NBP_261	260.8	153.4	68.64	0.20144	0.10077
NBP_289	289.1	161.5	66.00	0.22257	0.11141
NBP_313	313.0	171.2	63.86	0.25704	0.12795
NBP_338	337.7	178.9	62.48	0.30947	0.15144
NBP_362	362.5	190.3	61.19	0.37896	0.18006
NBP_388	387.6	202.2	59.79	0.46880	0.21393
NBP_412	412.3	215.0	57.60	0.58417	0.25268

Buttons: Data, Correlations, **Tables**, Property Plot, Distribution Plot, Composite Plot, Plot Summary, Notes

Buttons: Delete, Name: Blend-1, Blend Was Calculated

Use the vertical scroll bar to view the components which are not currently visible in the Component Physical Properties table.

### Viewing the Oil Distributions

- To view the distribution data, select Oil Distributions from the Table Type drop-down list. The **Tables** tab is modified as shown below.

Figure 2.33

Blend: Blend-1

Table Type: Oil Distributions

Table Control: Basis: Liquid Volume

Oil: Blend-1

Cut Input Information

Name	End T [F]
Oil Gas	50.00
Li St Run	158.0
Naphtha	356.0
Kerosene	464.0
Light Diesel	554.0
Heavy Diesel	644.0
Atm Gas Oil	698.0
Residue	2192

Cut Distributions

Name	Begin T [F]	End T [F]	Fraction
Li St Run	100.3	158.0	0.033
Naphtha	158.0	356.0	0.172
Kerosene	356.0	464.0	0.129
Light Diesel	464.0	554.0	0.089
Heavy Diesel	554.0	644.0	0.083
Atm Gas Oil	644.0	698.0	0.049
Residue	698.0	1441	0.444

Buttons: Data, Correlations, **Tables**, Property Plot, Distribution Plot, Composite Plot, Plot Summary, Notes

Buttons: Delete, Name: Blend-1, Blend Was Calculated



At the bottom of the Cut Input Information group, the Straight Run radio button is selected, and HYSYS provides default TBP cut point temperatures for each Straight Run product. The Cut Distributions table shows the Fraction of each product in the Blend. Since Liquid Vol is the current Basis in the Table Control group, the products are listed according to liquid volume fraction.

These fractions can be used to estimate the product flow rates for the fractionation column. For example, the Kerosene liquid volume fraction is 0.129. With 100,000 bbl/day of crude feeding the tower, the Kerosene production is expected at  $100,000 * 0.129 = 12,900$  or roughly 13,000 bbl/day.

If you want, you can investigate other reporting and plotting options by selecting another Table Type or by viewing information on the other tabs in the Blend property view.

2. When you are finished, close the Blend view to return to the Oil Characterization view. Now that the Blend has been calculated, the next task is to install the oil.

## Installing the Oil


The last step in the oil characterization procedure is to install the oil, which accomplishes the following:

- The petroleum hypoccomponents are added to the fluid package.
  - The calculated Light Ends and Oil composition are transferred to a material stream for use in the simulation.
1. On the Oil Characterization view, click the **Install Oil** tab.
  2. In the Stream Name column, click in the top blank cell.



3. Type the name Preheat Crude, then press the ENTER key. HYSYS creates a new stream named Preheat Crude in the flowsheet associated with the fluid package associated with this oil.

Figure 2.34



In this case, there is only one fluid package (Basis-1) and one flowsheet (the main flowsheet), so the stream is created in the main flowsheet. HYSYS assigns the composition of the calculated oil and light ends to stream Preheat Crude. The properties of the new stream can be viewed from the Simulation environment.

The characterization procedure is now complete.




Leave Oil Environment icon

4. Return to the Basis environment by clicking the **Leave Oil Environment** icon.
5. Click the **Components** tab of the Simulation Basis Manager view.
6. Select Component List - 1 from the list in the Component Lists group. Click the **View** button to open the component list property view.



- The hypocomponents generated during the oil characterization procedure now appear in the Selected Components group.

Figure 2.35




## Viewing Component Properties

To view the properties of one or more components, select the component(s) and click the **View Component** button. HYSYS opens the property view(s) for the component(s) you selected.

Press and hold the **CTRL** key to select more than one component.

- In the Selected Components list, select H2O and NBP[0]113\*.
- Click the **View Component** button. The property views for these two components appear.

Figure 2.36





See [Chapter 3 - Hypotheticals](#) in the Simulation Basis manual for more information on cloning library components.

The Component property view provides you with complete access to the component information. For pure components like H<sub>2</sub>O, the information is provided for viewing only. You cannot modify any parameters for a library (pure) component, however, HYSYS allows you to clone a library component into a Hypothetical component, which you can then modify as required.


The petroleum hypocomponent shown here is an example of a hypothetical component. You can modify any of the parameters listed for this component. For this example, the properties of the hypothetical components generated during the oil characterization are not changed.



Basis Manager icon

3. Close each of these two component property views.
4. The fluid package is now completely defined, so close the Component List view. The Simulation Basis Manager view should again be visible; if not, click the **Basis Manager** icon to access it.
5. Click the **Fluid Pkgs** tab to view a summary of the new fluid package.

Figure 2.37



The list of Current Fluid Packages displays the new fluid package, Basis-1, showing the number of components (NC) and property package (PP). The fluid package contains a total of 44 components:

- 6 library (pure) components (H<sub>2</sub>O plus five Light Ends components)
- 38 petroleum hypocomponents

The new fluid package is assigned by default to the Main Flowsheet, as shown in the Flowsheet-Fluid Pkg Associations group. Next you will install streams and operations in the Main Simulation environment.



## 2.2.4 Entering the Simulation Environment




Simulation Environment icon

- To leave the Basis environment and enter the Simulation environment, do **one** of the following:
  - Click the **Enter Simulation Environment** button on the Simulation Basis Manager view.
  - Click the **Simulation Environment** icon.

When you enter the Simulation Environment, the initial view that appears depends on your current preference setting for the Initial Build Home View.

Three initial views are available: PFD, Workbook and Summary. Any or all of these can be displayed at any time, however, when you first enter the Simulation Environment, only one appears. For this example, the initial Home View is the Workbook (HYSYS default setting).

Figure 2.38





There are several things to note about the Main Simulation Environment. In the upper right corner, the Environment has changed from Basis to Case (Main). A number of new items are now available on the menu and toolbar, and the Workbook and Object Palette are open on the Desktop. These latter two objects are described below.


Objects	Description
Workbook	A multiple-tab view containing information regarding the objects (streams and unit operations) in the simulation case. By default, the Workbook has four tabs, namely Material Streams, Compositions, Energy Streams and Unit Ops. You can edit the Workbook by adding or deleting tabs, and changing the information displayed on any tab.
Object Palette	A floating palette of buttons which can be used to add streams and unit operations.

You can toggle the palette open or closed by pressing **F4**, or by selecting Open/Close Object Palette from the Flowsheet menu.

Also notice that the name of the stream (Preheat Crude) you created during the Oil characterization procedure appears in the Workbook, and the white Object Status window at the very bottom of the environment view shows that the stream has an unknown pressure. As you specify the conditions of Preheat Crude, the message displayed in the Object Status window is updated appropriately. Before specifying the feed conditions, you can view the stream composition, which was calculated by the Oil characterization.

## Viewing the Feed Composition

1. In the Workbook, click the **Compositions** tab to view the composition of the streams.





The light ends and petroleum hydrocomponents are listed by Mole Fraction. To view the components which are not currently visible, use the up and down arrow keys or the vertical scroll bar to advance down the component list.

Before proceeding any further to install streams or unit operations, save your case.



Save icon

2. Do one of the following:
  - Click the **Save** icon on the toolbar.
  - Select **Save** from the **File** menu.
  - Press **CTRL S**.

If this is the first time you have saved your case, the Save Simulation Case As view appears. By default, the File Path is the cases sub-directory in your HYSYS directory.

If you enter a name that already exists in the current directory, HYSYS ask you for confirmation before overwriting the existing file.

3. In the **File Name** field, type a name for the case, for example **REFINING**. You do not have to enter the .hsc extension; HYSYS adds it automatically.
4. Once you have entered a file name, press the **ENTER** key or click the **OK** button. When you click the **Save** button, HYSYS saves the case under the name you gave it. The Save As view does not appear again unless you choose to give it a new name using the **Save As** command.

## 2.2.5 Using the Workbook



Workbook icon

Click the Workbook icon on the toolbar to ensure the Workbook view is active.


### Specifying the Feed Conditions

In general, the first task in the Simulation environment is to install one or more feed streams, however, the stream Preheat Crude was already installed during the oil characterization procedure. At this point, your current location should be the Compositions tab of the Workbook view.



1. Click the **Material Streams** tab. The preheated crude enters the pre-fractionation train at 450°F and 75 psia.
2. In the Preheat Crude column, click in the **Temperature** cell and type 450. HYSYS displays the default units for temperature, in this case °F.

Figure 2.40



Name	Preheat Crude	** New **
Vapour Fraction	<empty>	
Temperature [F]	450	F
Pressure [psia]	<empty>	


When you press **ENTER** after entering a stream property, you are advanced down one cell in the Workbook only if the cell below is <empty>. Otherwise, the active cell remains in its current location.

3. Since this is the correct unit, press the ENTER key. HYSYS accepts the temperature. HYSYS advances to the **Pressure** cell.

If you know the stream pressure in another unit besides the default of psia, HYSYS will accept your input in any one of a number of different units and automatically convert the value to the default. For example, the pressure of Preheat Crude is 5.171 bar, but the default units are psia.

4. In the **Pressure** cell, type 5.171.
5. Press SPACEBAR. The field containing the active cell units becomes active.
6. Begin typing 'bar'. The field opens a drop-down list and scrolls to the unit(s) most closely matching your input.

Figure 2.41



Name	Preheat Crude	** New **
Vapour Fraction	0.3768	
Temperature [F]	450.0	
Pressure [psia]	5.171	bar
Molar Flow [lbmole/hr]	<empty>	bar
Mass Flow [lb/hr]	<empty>	N/m2
Liquid Volume Flow [barrel/day]	<empty>	atm
Heat Flow [Btu/hr]	<empty>	kg/cm2
		psia
		lb/ft2

Alternately, you can specify the unit simply by selecting the unit in the drop-down list.

7. Once 'bar' is selected, press the ENTER key. HYSYS accepts the pressure and automatically converts to the default unit, psia.
8. Click in the **Liquid Volume Flow** cell, then type 1e5. The stream flow is entered on a volumetric basis, in this case 100,000 bbl/day.
9. Press the ENTER key.



If HYSYS does not flash the stream, ensure that the Solver Active icon in the tool bar is selected.



Solver Active icon

The stream is now completely defined, so HYSYS flashes it at the conditions given to determine the remaining properties. The properties of Preheat Crude are shown below. The values you specified are a different colour (blue) than the calculated values (black).

Figure 2.42

Name	Preheat Crude	** New **
Vapour Fraction	0.1292	
Temperature [F]	450.0	
Pressure [psia]	75.00	
Molar Flow [lbmole/hr]	3814	
Mass Flow [lb/hr]	1.144e+006	
Liquid Volume Flow [barrel/day]	1.000e+005	
Heat Flow [Btu/hr]	-7.619e+008	

Material Streams | Compositions | Energy Streams | Unit Ops

ProductBlock\_Preheat Crude  
FeederBlock\_Preheat Crude

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0

The next task is to install and define the utility steam streams that will be attached to the fractionation tower later.

## Installing the Utility Steam Streams

1. On the **Material Streams** tab, click in the header cell labeled **\*\*New\*\***.
2. Type the new stream name Bottom Steam, then press ENTER. HYSYS creates the new stream.
3. In the **Temperature** cell, enter 375°F.
4. In the **Pressure** cell, enter 150 psia.

HYSYS accepts blank spaces within a stream or operation name.

Figure 2.43

Name	Preheat Crude	Bottom Steam	** New **
Vapour Fraction	0.1292	<empty>	
Temperature [F]	450.0	375.0	
Pressure [psia]	75.00	150.0	
Molar Flow [lbmole/hr]	3814	<empty>	
Mass Flow [lb/hr]	1.144e+006	<empty>	
Liquid Volume Flow [barrel/day]	1.000e+005	<empty>	
Heat Flow [Btu/hr]	-7.619e+008	<empty>	

Material Streams | Compositions | Energy Streams | Unit Ops

ProductBlock\_Bottom Steam  
FeederBlock\_Bottom Steam

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0



5. In the **Mass Flow** cell, enter 7500 lb/hr.
6. Create a new utility stream called Diesel Steam.
7. Define the conditions of this stream as follows:
  - Temperature 300°F
  - Pressure 50 psia
  - Mass Flow 3000 lb/hr.

The Workbook view appears as shown below.

**Figure 2.44**

The screenshot shows the 'Workbook - Case (Main)' window with a table of stream properties. The table has four columns: Name, Preheat Crude, Bottom Steam, and Diesel Steam. The rows include Vapour Fraction, Temperature [F], Pressure [psia], Molar Flow [lbmole/hr], Mass Flow [lb/hr], Liquid Volume Flow [barrel/day], and Heat Flow [Btu/hr]. The Diesel Steam column has a highlighted cell for Mass Flow with the value 3000. Below the table are tabs for Material Streams, Compositions, Energy Streams, and Unit Ops. The Material Streams tab is active, showing ProductBlock\_Diesel Steam and FeederBlock\_Diesel Steam. There are also checkboxes for 'Include Sub-Flowsheets' and 'Show Name Only', and a field for 'Number of Hidden Objects'.

Name	Preheat Crude	Bottom Steam	Diesel Steam
Vapour Fraction	0.1292	<empty>	<empty>
Temperature [F]	450.0	375.0	300.0
Pressure [psia]	75.00	150.0	50.00
Molar Flow [lbmole/hr]	3814	<empty>	<empty>
Mass Flow [lb/hr]	1.144e+006	7500	3000
Liquid Volume Flow [barrel/day]	1.000e+005	<empty>	<empty>
Heat Flow [Btu/hr]	-7.619e+008	<empty>	<empty>
Name	"New"		
Vapour Fraction			

**Material Streams** Compositions Energy Streams Unit Ops

ProductBlock\_Diesel Steam  
FeederBlock\_Diesel Steam

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects:

## Providing Compositional Input


Now that the utility stream conditions have been specified, the next task is to input the compositions.

1. Click the **Compositions** tab in the Workbook. The components are listed by Mole Fraction by default.
2. In the Bottom Steam column, click in the input cell for the first component, H<sub>2</sub>O.



The Input Composition for Stream view is Modal, indicated by the absence of the Minimize/Maximize icons in the upper right corner. When a Modal view is visible, you are unable to move outside the view until you are finish with it, by clicking either the Cancel or OK button.

3. Since the stream is all water, type 1 for the H2O mole fraction, then press ENTER. The Input Composition for Stream view appears, allowing you to complete the compositional input.



The Input Composition for Stream view allows you to specify a stream composition quickly and easily. The following table lists and describes the features available on this view:

Features	Description
<b>Compositional Basis Radio Buttons</b>	You can input the stream composition in some fractional basis other than Mole Fraction, or by component flows, by selecting the appropriate radio button before providing your input.
<b>Normalizing</b>	<p>The Normalizing feature is useful when you know the relative ratios of components (2 parts N2, 2 parts CO2, etc.) Rather than manually converting these ratios to fractions summing to one, enter the numbers of parts for each component and click the Normalize button. HYSYS computes the individual fractions to total 1.0.</p> <p>Normalizing is also useful when you have a stream consisting of only a few components. Instead of specifying zero fractions (or flows) for the other components, enter the fractions (or the actual flows) for the non-zero components, leaving the others &lt;empty&gt;. Click the Normalize button, and HYSYS forces the other component fractions to zero.</p>
<b>Calculation status/colour</b>	<p>As you input the composition, the component fractions (or flows) initially appear in red, indicating the final composition is unknown. These values become blue when the composition has been calculated. Three scenarios result in the stream composition being calculated:</p> <ul style="list-style-type: none"><li>• Input the fractions of all components, including any zero components, such that their total is exactly 1.0000, then click the OK button.</li><li>• Input the fractions (totalling 1.000), flows or relative number of parts of all non-zero components, then click the Normalize button then the OK button.</li><li>• Input the flows or relative number of parts of all components, including any zero components, then click the OK button.</li></ul>

These are the default colours; yours can appear differently depending on your settings on the Colours page of the Session Preferences view.



This stream is pure water, therefore, there is no need to enter fractions for any other components.


4. Click the **Normalize** button, and all other component fractions are forced to zero.
5. Click the **OK** button. HYSYS accepts the composition, and you are returned to the Workbook view.

The stream is now completely defined, so HYSYS flashes it at the conditions given to determine the remaining properties.

6. Repeat steps #2 to #5 for the other utility stream, Diesel Steam.
7. Click the **Material Streams** tab. The calculated properties of the two utility streams appear here.

If you want to delete a stream, move to the Name cell for the stream, then press **DELETE**. HYSYS ask for confirmation of your action.

Figure 2.46



Name	Preheat Crude	Bottom Steam	Diesel Steam
Vapour Fraction	0.1292	1.0000	1.0000
Temperature [F]	450.0	375.0	300.0
Pressure [psia]	75.00	150.0	50.00
Molar Flow [lbmole/hr]	3814	416.3	166.5
Mass Flow [lb/hr]	1.144e+006	7500	3000
Liquid Volume Flow [barrel/day]	1.000e+005	514.6	205.8
Heat Flow [Btu/hr]	-7.619e+008	-4.222e+007	-1.697e+007
Name	"New"		
Vapour Fraction			

Material Streams Compositions Energy Streams Unit Ops

ProductBlock\_Preheat Crude  
FeederBlock\_Preheat Crude

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0

Next, you will learn alternative methods for creating a new stream.

8. To add the third utility stream, do any **one** of the following:
  - Press **F11**.
  - From the **Flowsheet** menu, select **Add Stream**.
  - Double-click the **Material Stream** icon on the Object Palette.
  - Click the **Material Stream** icon on the Object Palette, then click on the Palette's **Add Object** icon.



Material Stream icon



Add Object icon

Each of these four methods displays the property view for the new stream, which is named according to the Auto Naming setting in your Preferences. The default setting names new material streams with numbers, starting at 1, and energy streams starting at Q-100.

9. In the stream property view, click in the **Stream Name** cell and rename the stream AGO Steam.
10. Press **ENTER**.



Both of the temperature and pressure parameters are in the default units, so you do not need to change the unit with the values.

Do not enter a flow, it is entered through the Composition page.

11. In the **Temperature** cell, enter 300.
12. In the **Pressure** cell, enter 50.

Figure 2.47

Worksheet	
Stream Name	AGO Steam
Vapour / Phase Fraction	<empty>
Temperature [F]	300.00
Pressure [psia]	50.000
Molar Flow [lbmole/hr]	<empty>
Mass Flow [lb/hr]	<empty>
Std Ideal Liq Vol Flow [barrel/day]	<empty>
Molar Enthalpy [Btu/lbmole]	<empty>
Molar Entropy [Btu/lbmole-F]	<empty>
Heat Flow [Btu/hr]	<empty>
Liq Vol Flow @Std Cond [barrel/day]	<empty>
Fluid Package	Basis-1

Worksheet Attachments Dynamics

Unknown Compositions

Delete Define from Other Stream...

13. Select the **Composition** page to begin the compositional input for the new stream.

Figure 2.48

Worksheet	
H2O	Mole Fractions <empty>
Propane	<empty>
i-Butane	<empty>
n-Butane	<empty>
i-Pentane	<empty>
n-Pentane	<empty>
NBP[0]113°	<empty>
NBP[0]139°	<empty>
NBP[0]164°	<empty>
NBP[0]188°	<empty>

Total 0.00000

Edit... Edit Properties... Basis...

Worksheet Attachments Dynamics

Unknown Compositions

Delete Define from Other Stream...

The current Composition Basis setting is set to the Preferences Default of Mole Fractions. The stream composition is entered on a mass basis.


14. Click the **Edit** button. The Input Composition for Stream view appears.



15. In the Composition Basis group, select the **Mass Flows** radio button.
16. Click in the compositional cell for H<sub>2</sub>O.
17. Type 2500 for the steam mass flow, then press ENTER. As there are no other components in this stream, the compositional input is complete.
18. Click the **OK** button to close the view and return to the stream property view.

Since only H<sub>2</sub>O contain any significant value, HYSYS automatically forces all other components' value to be zero.

**Figure 2.49**



HYSYS performs a flash calculation to determine the unknown properties of AGO Steam, as shown by the status indicator displaying 'OK'. You can view the properties of each phase using the horizontal scroll bar in the matrix or by re-sizing the property view. In this case, the stream is superheated vapour, so no Liquid phase exists and the Vapour phase is identical to the overall phase. To view the vapour compositions for AGO Steam, scroll to the right by clicking the right scroll arrow, or by click and dragging the scroll button.

**The compositions are currently displayed by Mass Flows. You can change this by clicking the Basis button and choosing another Composition Basis radio button.**

19. Close the AGO Steam property view.



## 2.2.6 Installing Unit Operations

Now that the feed and utility streams are known, the next task is to install the necessary unit operations for processing the crude oil.

### Installing the Separator


The first operation is a Separator, used to split the feed stream into its liquid and vapour phases. As with most commands in HYSYS, installing an operation can be accomplished in a number of ways. One method is through the Unit Ops tab of the Workbook.



Workbook icon

1. Click the **Workbook** icon to ensure the Workbook is the active view.
2. Move to the **Unit Ops** tab.
3. Click the **Add UnitOp** button. The UnitOps view appears, listing all available unit operations.
4. In the Categories group, select the **Vessels** radio button. HYSYS produces a filtered list of unit operations, showing only those in the current category.
5. Add the separator by doing **one** of the following:
  - Select Separator in the list of Available Unit Operations, and click the **Add** button or the **ENTER** key.
  - Double-click on Separator.


Figure 2.50





The property view for the separator appears in the figure below.

Figure 2.51



HYSYS provides the default name V-100 for the separator. The default naming scheme for unit operations can be changed in your Session Preferences.

A unit operation property view contains all the information defining the operation, organized into tabs and pages. The Design, Rating and Worksheet tabs appear for most operations. Property views for more complex operations contain more tabs.

Many operations, like the separator, accept multiple feed streams. Whenever you see a matrix like the one in the Inlets group, the operation accepts multiple stream connections at that location. When the matrix is active, you can access a drop-down list of available streams.


6. Click in the **Name** field, type PreFlash, then press ENTER. The status indicator at the bottom of the view shows that the operation requires a feed stream.
7. In the Inlets matrix, click in the <<Stream>> cell.
8. Click the down arrow ▼ to open the drop-down list of available streams.



Alternatively, you could have made the connection by typing the exact stream name in the cell, and pressing **ENTER**.


9. Select **Preheat Crude** from the list. Preheat Crude appears in the Inlets matrix, and the <<Stream>> label is automatically moved down to a new empty cell. The status indicator now displays 'Requires a product stream'.

Figure 2.52



10. Click in the **Vapour Outlet** field, or press TAB to move to the field.
11. Type PreFlashVap in the field, then press ENTER. This stream does not yet exist, so HYSYS creates this new stream.
12. Click in the **Liquid Outlet** field and type PreFlashLiq. HYSYS creates another new stream.

Figure 2.53






An Energy stream could be attached to heat or cool the vessel contents, however, for the purposes of this example, the energy stream is not required.

Since there is no energy stream attached to the separator, no Optional Heat Transfer information is required.

The status indicator displays a green OK message, showing that the operation and attached streams are completely calculated.

13. Select the **Parameters** page. The default **Delta P** (pressure drop) of zero is acceptable for this example. The **Liquid Level** is also acceptable at its default value.

Figure 2.54



14. To view the calculated outlet streams, click the **Worksheet** tab. This is a condensed Workbook displaying only those streams attached to the operation.


Figure 2.55

Name	Preheat Crude	PreFlashLiq	PreFlashVap
Vapour	0.1292	0.0000	1.0000
Temperature [F]	450.0	450.0	450.0
Pressure [psia]	75.00	75.00	75.00
Molar Flow [lbmole/hr]	3814	3321	492.9
Mass Flow [lb/hr]	1.144e+006	1.080e+006	6.454e+004
Std Ideal Liq Vol Flow [barrel/day]	1.000e+005	9.372e+004	6282
Molar Enthalpy [Btu/lbmole]	-1.998e+005	-2.175e+005	-8.049e+004
Molar Entropy [Btu/lbmole-F]	266.0	288.8	112.4
Heat Flow [Btu/hr]	-7.619e+008	-7.222e+008	-3.967e+007



15. Now that the separator is completely known, close the PreFlash view and the UnitOps view, and return to the Workbook view. The new separator appears on the **Unit Ops** tab.

Figure 2.56



The matrix shows the operation Name, its Object Type, the attached streams (Inlet and Outlet), whether it is Ignored, and its Calculation Level.

### Optional Methods for Accessing Property Views

When you click the View UnitOp button, the property view for the operation occupying the active row in the matrix opens. Alternatively, by double-clicking on any cell (except Inlet and Outlet) associated with the operation, you also open its property view.

You can also open the property view for a stream directly from the Unit Ops tab of the Workbook. When any of the Name, Object Type, Ignored or Calc. Level cells are active, the display field at the bottom of the view displays all streams attached to the current operation. Currently, the Name cell for PreFlash is active, and the display field displays the three streams attached to this operation. To open the property view for one of the streams attached to the separator (such as Preheat Crude), do **one** of the following:

- Double-click on Preheat Crude in the display field at the bottom of the view.
- Double-click on the **Inlet** cell for PreFlash. The property view for the first listed feed stream opens. In this case, Preheat Crude is the only feed stream, so its property view also opens.



# 2.2.7 Using Workbook Features

Before you install the remaining operations, you will examin a number of Workbook features that allow you to access information quickly and change how information appears.

## Accessing Unit Operations from the Workbook

Return to the Material Streams tab of the Workbook.


Any utilities attached to the stream with the Workbook active are also displayed in (and are accessible through) this display field.

There are a number of ways to open the property view for an operation directly from the Workbook besides using the Unit Ops tab.

When your current location is a Workbook streams tab (Material Streams, Compositions and Energy Streams tabs), the field at the bottom of the Workbook view displays the operations to which the current stream is attached. In this display field, you can click on any cell associated with the stream.

For example, if you click in any cell for Preheat Crude, the field displays the name of the operation, PreFlash, to which this stream is attached. The display field also displays FeederBlock\_Preheat Crude, because the Preheat Crude stream is a boundary stream. To access the property view for the PreFlash operation, double-click on PreFlash. The operation property view appears.

Figure 2.57





## Adding a Tab to the Workbook


When the Workbook is active, the Workbook item appears in the HYSYS menu bar. This item allows you to customize the Workbook.

In this section, you will create a new Workbook tab that displays only stream pressure, temperature, and flow.

1. Do one of the following:
  - From the **Workbook** menu, select **Setup**.
  - Object inspect (right-click) the Material Streams tab in the Workbook, then select **Setup** from the menu that appears.

The Workbook Setup view appears.

Figure 2.58




The four existing tabs are listed in the Workbook Tabs area. When you add a new tab, it is inserted *before* the selected tab (currently Material Streams). You will insert the new tab before the Compositions tab.

2. In the Workbook Tabs group list, select **Compositions**.




3. Click the **Add** button. The New Object Type view appears.

Figure 2.59



4. Click the + beside Stream, select Material Stream from the branch, then click the **OK** button. You return to the Setup view, and the new tab appears after the existing **Material Streams** tab.
5. In the Tab Contents Object group, click in the **Name** field.
6. Change the name of the new tab to P,T,Flow to better describe the tab contents.

Figure 2.60



The next task is to customize the tab by removing the variables that are not required.


7. In the Variables group, click on the first variable, Vapour Fraction.
8. Press and hold the CTRL key.



9. Click on the other variables, Molar Flow, Mass Flow, Heat Flow and Molar Enthalpy. These four variables are now highlighted.
10. Release the CTRL key.
11. Click the **Delete** button to remove them from this **Workbook** tab *only*. The finished Setup view appears below.


If you want to remove variables from another tab, you must edit each tab individually.

Figure 2.61



12. Click the **Close** icon to return to the Workbook view and see the new tab.

Figure 2.62



13. Save your case by doing **one** of the following:

- Click the **Save** icon on the tool bar.
- Select **Save** from the **File** menu.
- Press **CTRL S**.



Save icon



## 2.2.8 Using the PFD




PFD icon

The PFD is the other main view used in HYSYS. The PFD item appears in the HYSYS menu bar whenever the PFD is active.

To open the PFD, click the **PFD** icon on the tool bar. The PFD view should appear similar to the one shown below, except some stream icons may overlap each other.

Figure 2.63



As a graphical representation of your flowsheet, the PFD shows the connections among all streams and operations, also known as 'objects'. Each object is represented by a symbol, also known as an 'icon'. A stream icon is an arrow pointing in the direction of the flow, while an operation icon is a graphic representing the actual physical operation. The object name, also known as a 'label', appears near each icon.

The PFD shown above has been rearranged by moving the three utility stream icons below and to the left of the Separator. To move an icon, click and drag it to the new location.

**You can click and drag either the icon (arrow) itself, or the label (stream name), as these two items are grouped together.**

Like any other non-modal view, the PFD view can be re-sized by clicking and dragging anywhere on the outside border.





Size Mode icon



Zoom Out 25% icon



Display Entire PFD icon



Zoom In 25% icon

Keep in mind that these are the HYSYS default colours; you can change the colours in the Session Preferences.

Other things you can do while the PFD is active include the following:

- Access commands and features through the PFD toolbar.
- Open the property view for an object by double-clicking on its icon.
- Move an object by click and dragging it to the new location.
- Access “pop-up” summary information for an object simply by placing the cursor over it.
- Change an icon's size by clicking the Size Mode icon, clicking on the icon, and click and dragging the sizing handles that appear around the icon.
- Display the Object Inspection menu for an object by placing the cursor over it, and right-clicking. This menu provides access to a number of commands associated with the particular object.
- Zoom in and out, or display the entire flowsheet in the PFD window by clicking the zoom buttons at the bottom left corner of the PFD view.

Some of these functions are illustrated here; for more information, see [Chapter 7.25 - PFD](#) in the **User Guide**.

## Calculation Status

Before proceeding, you will examine a feature of the PFD that allows you to trace the calculation status of the objects in your flowsheet. If you recall, the status indicator at the bottom of the property view for a stream or operation displays one of three possible states for the object:

Status	Description
<b>Red Status</b>	A major piece of defining information is missing from the object. For example, a feed or product stream is not attached to a separator. The status indicator is red, and an appropriate warning message appears.
<b>Yellow Status</b>	All major defining information is present, but the stream or operation has not been solved because one or more degrees of freedom is present, for example, a cooler where the outlet stream temperature is unknown. The status indicator is yellow, and an appropriate warning message appears.
<b>Green Status</b>	The stream or operation is completely defined and solved. The status indicator is green, and an OK message appears.

When you are in the PFD, the streams and operations are colour-coded to indicate their calculation status. The inlet separator is completely calculated, so its normal colours appear. While installing the remaining operations through the PFD, their colours (and status) changes appropriately as information is supplied.



The icons for all streams installed to this point are dark blue, indicating they have been flashed.

A similar colour scheme is used to indicate the status of streams. For material streams, a dark blue icon indicates the stream has been flashed and is entirely known. A light blue icon indicates the stream cannot be flashed until some additional information is supplied. Similarly, a dark red icon is for an energy stream with a known duty, while a purple icon indicates an unknown duty.

## Installing the Crude Furnace

In this section, you will install a crude furnace. The furnace is modeled as a Heater.

1. Ensure the Object Palette is visible (if it is not, press F4).

You will add the furnace to the right of the PreFlash Separator, so make some empty space available by scrolling to the right using the horizontal scroll bar.

2. In the Object Palette, click the **Heater** icon. The cursor changes to a special cursor, with a black frame and plus (+) symbol attached to it. The frame indicates the size and location of the operation icon.
3. Position the cursor over the PFD to the right of the separator.




Heater icon (Red)



Cooler icon (Blue)

Figure 2.64



Notice the heater has red status (colour), indicating that it requires feed and product streams.


4. Click to 'drop' the heater onto the PFD. HYSYS creates a new heater with a default name, E-100.

Next you will change the heater icon from its default to one more closely resembling a furnace.



5. Right-click the heater icon. The Object Inspect menu appears.
6. Select **Change Icon** from the menu. The Select Icon view appears.

Figure 2.65



Furnace icon




Attach Mode icon

7. Click the **WireFrameHeater5** icon (scroll to the right), then click the **OK** button. The new icon appears in the PFD.

## Attaching Streams to the Furnace

1. Click the **Attach** icon on the PFD tool bar to enter Attach mode.
2. Position the cursor over the right end of the PreFlashLiq stream icon. A small box appears at the cursor tip.

Figure 2.66




When you are in Attach mode, you are not able to move objects in the PFD. To return to Move mode, click the Attach button again. You can temporarily toggle between Attach and Move mode by holding down the **CTRL** key.

3. With the pop-up 'Out' visible, click and hold the mouse button. The white box becomes black, indicating that you are beginning a connection.
4. Drag the cursor toward the left (inlet) side of the heater. A trailing line appears between the PreFlashLiq stream icon and the cursor, and a connection point appears at the Heater inlet.



5. Place the cursor near the connection point of the heater, and the trailing line snaps to that point. As well, a white box appears at the cursor tip, indicating an acceptable end point for the connection.

Figure 2.67




Break Connection icon

If you make an incorrect connection:

1. Click the **Break Connection** icon on the PFD toolbar.
2. Move the cursor over the stream line connecting the two icons. A checkmark attached to the cursor appears, indicating an acceptable connection to break.
3. Click once to break the connection.


6. Release the mouse button, and the connection is made to the heater inlet.
7. Position the cursor over the right end of the heater icon. The connection point and pop-up 'Product' appears.
8. With the pop-up visible, click and hold the mouse button. The white box again becomes black.
9. Move the cursor to the right of the heater. A stream icon appears with a trailing line attached to the heater outlet. The stream icon indicates that a new stream is being created.

Figure 2.68



10. With the stream icon visible, release the mouse button. HYSYS creates a new stream with the default name 1.
11. Create the Heater energy stream, starting the connection from the bottom left connection point on the Heater icon labeled 'Energy Stream'. The new stream is automatically named Q-100, and the heater now has yellow (warning) status. This status indicates that all necessary connections have been made, but the attached streams are not entirely known.

Figure 2.69



12. Click the **Attach** icon again to return to Move mode.




The heater outlet and energy streams are unknown at this point, so they appear light blue and purple, respectively.

## Modifying Furnace Properties

1. Double-click the Heater icon to open its property view.
2. Click the **Design** tab, then select the **Connections** page. The names of the Inlet, Outlet and Energy streams appear in the appropriate fields.

Figure 2.70




3. In the **Name** field, change the operation name to Furnace.
4. Select the **Parameters** page.



5. In the **Delta P** field, enter 10 psi, then close the view.


Figure 2.71



The Furnace has one available degree of freedom. Either the outlet stream temperature or the amount of duty in the energy stream can be specified. In this case, you will specify the outlet temperature.

6. Double-click the outlet stream icon (1) to open its property view.
7. In the **Stream Name** field, change the name to Hot Crude.
8. In the **Temperature** field, specify a temperature of 650°F.

Figure 2.72






The remaining degree of freedom in the Furnace has now been used, so HYSYS can flash Hot Crude and determine its remaining properties.

9. Close the view to return to the PFD view. The Furnace now has green status, and all attached streams are known.
10. Double-click on the energy stream icon (Q-100) to open its property view. The required heating duty calculated by HYSYS appears in the **Heat Flow** cell.
11. In the **Stream Name** cell, rename this energy stream Crude Duty, then close the property view.

Figure 2.73



## Installing the Mixer

In this section, you will install a Mixer operation. The Mixer is used to combine the hot crude stream with the vapours bypassing the furnace. The resulting stream is the feed for the crude column.




Mixer icon

1. Make some empty space available to the right of the Furnace using the horizontal scroll bar. Move other objects if necessary.
2. Click the **Mixer** icon on the Object Palette.
3. Position the cursor over the PFD to the right of the Hot Crude stream icon.
4. Click to 'drop' the mixer onto the PFD. HYSYS creates a new mixer with the default name MIX-100.
5. Press and hold the CTRL key to temporarily enable the Attach mode while you make the mixer connections (you will not release it until step #13).
6. Position the cursor over the right end of the PreFlashVap stream icon. The connection point and pop-up 'Out' appears.




Multiple connection points appear because the Mixer accepts multiple feed streams.



7. With the pop-up visible, click and hold the mouse button, then drag the cursor toward the left (inlet) side of the mixer. Multiple connection points appear at the mixer inlet.
8. Place the cursor near the inlet area of the mixer, and when the white box appears at the cursor tip, release the mouse button to make the connection.
9. Repeat steps #6 to #8 to connect the Hot Crude stream to the Mixer.
10. Position the cursor over the right end of the mixer icon. The connection point and pop-up 'Product' appears.
11. With the pop-up visible, click and drag to the right of the mixer. A white stream icon appears, with a trailing line attached to the mixer outlet.
12. With the white stream icon visible, release the mouse button. HYSYS creates a new stream with the default name 1.
13. Release the CTRL key to leave Attach mode.
14. Double-click on the outlet stream icon 1 to access its property view. When you created the mixer outlet stream, HYSYS automatically combined the two inlet streams and flashed the mixture to determine the outlet conditions.
15. In the **Stream Name** cell, rename the stream TowerFeed, then close the view.

Figure 2.74



16. Double-click the mixer icon, MIX-100. Change the name to Mixer, then close the view.



## Resizing Icons in the PFD


Resize icons in the PFD to make it easier to read.

1. Resize the PFD view by clicking and dragging the outside border.
2. Click the **Zoom All** icon to fill the PFD window, including any objects that were not visible previously. A possible view of the resized PFD appears in the figure below.



Zoom All icon


Figure 2.75



Size Mode icon

3. Click the **Size Mode** icon on the PFD toolbar.
4. Click the Furnace icon in the PFD. A frame with sizing handles appears around the icon.
5. Place the cursor over one of the sizing handles. The cursor changes to a double-ended sizing arrow.

Figure 2.76



6. With the sizing arrow visible, click and drag to resize the icon.
7. Click the **Size Mode** icon again to return to Move mode.



## Adding an Energy Stream

In this section, you will add an energy stream. Prior to installing the column, an energy stream must be created to represent the trim duty on stage 28 of the main tower.



Energy Stream icon



Save icon

1. Double-click on the **Energy Stream** icon on the Object Palette. HYSYS creates a new energy stream with the default name Q-100 and display its property view.
2. In the **Stream Name** field, change the name to Trim Duty.
3. Close the view.
4. Save your case by doing one of the following:
  - press **CTRL S**.
  - from the **File** menu, select **Save**.
  - click the **Save** icon.

## Installing the Column

If you choose to use the pre-built crude column template you still have to customize the column by modifying the various draw and return stages and default specifications. Although using the template eliminates the majority of the work over the next few pages, it is recommended that you work through these pages the first time you build a crude column in HYSYS. Once you are comfortable working with side equipment, try using the template. Instructions on using the crude column template are given in an annotation on the next page.

HYSYS has a number of pre-built column templates that you can install and customize by changing attached stream names, number of stages and default specifications, and adding side equipment. One of these templates is going to be used for this example (a crude column with three side strippers), however, a basic Refluxed Absorber column with a total condenser is installed and customized in order to illustrate the installation of the necessary side equipment.

1. Before installing the column, select **Preferences** from the HYSYS **Tools** menu. Click the **Simulation** tab.
2. On the **Options** page, ensure the **Use Input Experts** checkbox is checked, then close the view.





Refluxed Absorber icon

The Input Expert is a Modal view, indicated by the absence of the Maximize/Minimize icons. You cannot exit or move outside the Expert view until you supply the necessary information or click the Cancel button.

- Double-click the **Refluxed Absorber** icon on the Object Palette. The first page of the Input Expert appears.

Figure 2.77

To install this column using the pre-built crude column template:

- Double-click on the **Custom Column** icon on the Object Palette.
- On the view that appears, click the **Read an Existing Column Template** button. The Available Column Templates view appears, listing the template files \*.col that are provided in your HYSYS\template directory. Both 3- and 4-side stripper crude column templates are provided.
- Select **3sscruide.col** and click the **OK** button. The property view for the new column appears. You can now customize the new column.

When you install a column using a pre-built template, HYSYS supplies certain default information, such as the number of stages. The current active field is # Stages (Number of Stages), indicated by the thick border inside this field. There are some other points worth noting:

- These are theoretical stages, as the HYSYS default stage efficiency is one.
- If present, the Condenser and Reboiler are considered separate from the other stages, and are not included in the # Stages field.

## Entering Inlet Streams and Number of Trays


For this example, the main column has 29 theoretical stages.

- Enter 29 in the **# Stages** field.
- Advance to the Optional Inlet Streams table by clicking on the **<<Stream>>** cell, or by pressing TAB.




- Click the down arrow ▼ to open the drop-down list of available feeds.

Figure 2.78



- Select Tower Feed as the feed stream to the column. HYSYS supplies a default feed location in the middle of the Tray Section (TS), in this case stage 15 (indicated by 15\_Main TS). However, the feed stream needs to enter stage 28.
- In the Optional Inlet Streams group, click in the **Inlet Stage** cell for TowerFeed.
- Type 28 and press ENTER, or select 28\_Main TS from the drop-down list of stages.
- Click on <<Stream>> in the same table, which was automatically advanced down one cell when you attached the Tower Feed stream.
- From the Stream drop-down list, select the Trim Duty stream, which is also fed to stage 28.

Figure 2.79



- Advance to the **Bottom Stage Inlet** field by clicking on it or by pressing TAB.




10. In the **Bottom Stage Inlet** field, click the down arrow ▼ to open the drop-down list of available feeds.
11. From the list, select Bottom Steam as the bottom feed for the column.

## Entering Outlet Streams

In the Condenser group of the Input Expert view, the default condenser type is Partial. To the right of this group, there are two Overhead Outlets, vapour and liquid. In this case, the overhead vapour stream has no flow, and two liquid phases (hydrocarbon and water) are present in the condenser. The hydrocarbon liquid product is attached in the liquid Overhead Outlets field, while the water draw is attached using the Optional Side Draws table.

Figure 2.80



Although the overhead vapour product has zero flow, do not change the condenser to Total. At this time, only the Partial radio button allows you to specify a three-phase condenser.

1. Click in the top **Ovhd Outlets** field.
2. Enter Off Gas as the name of the overhead vapour product stream. HYSYS creates and attaches a new stream with this name.
3. Press TAB again to move to the bottom **Ovhd Outlets** field, and enter the new stream name Naphtha.


The next task is to attach the water draw stream to the condenser.

4. In the Optional Side Draws table, click in the <<Stream>> cell.
5. Enter the name of the draw stream, WasteH2O. HYSYS automatically places a hydrocarbon liquid (indicated by the L in the Type column) draw on stage 15. You will change this to a condenser water draw.




6. Click on the **Type** cell (the L) for the WasteH2O stream.
7. Specify a water draw by typing W then pressing ENTER, or by selecting W from the drop-down list.
8. Click on the **Draw Stage** cell (15\_Main TS) for the WasteH2O stream.
9. Select Condenser from the drop-down list. The condenser is now three-phase.

Figure 2.81



10. In the **Column Name** field, enter Atmos Tower.
  11. In the **Bottoms Liquid Outlet** field, type Residue to create a new stream.
  12. In the **Condenser Energy Stream** field, type Cond Duty to define a new stream. Press ENTER.
- The first page of the Input Expert should appear as shown below.

Figure 2.82





All stream attachments made on this page result in the creation of Column sub-flowsheet streams with the same names. For example, when the Main Flowsheet stream BottomSteam was attached as a feed, HYSYS automatically created an identical stream named BottomSteam to be used in the Column sub-flowsheet.


The Next button now becomes available, indicating sufficient information has been supplied to advance to the next page of the Input Expert.

13. Click the **Next** button to advance to the **Pressure Profile** page.

## Entering the Initial Estimate Values

1. On the **Pressure Profile** page, specify the following:
  - Condenser Pressure 19.7 psia
  - Condenser Pressure Drop 9 psi
  - Bottom Stage Pressure 32.7 psia

Figure 2.83




2. Click the **Next** button to advance to the **Optional Estimates** page. Although HYSYS does not usually require estimates to produce a converged column, good estimates result in a faster solution.



3. Specify the following:
  - Condenser 100°F
  - Top Stage 250°F
  - Bottom Stage 700°F

Figure 2.84



4. Click the **Next** button to advance to the fourth and final page of the Input Expert. This page allows you to supply values for the default column specifications that HYSYS has created.

In general, a refluxed absorber with a partial condenser has two degrees of freedom for which HYSYS provides two default specifications. For the two specifications given, overhead Vapour Rate is used as an active specification, and Reflux Ratio as an estimate only.


5. From the Flow Basis drop-down list, select Volume. All flow specifications are provided in barrels per day.



6. Specify the following:


- Vapour Rate 0
- Reflux Ratio 1.0.

Figure 2.85



7. Click the **Done** button. The Column property view appears.

Figure 2.86





## Adding Specification Values

1. On the Design tab, select the **Monitor** page.

The main feature of this page is that it displays the status of your column as it is being calculated, updating information with each iteration. You can also change specification values, and activate or de-activate specifications used by the Column solver, directly from this page.


The basic column has three available degrees of freedom. Currently, two Specifications are Active, so the overall Degrees of Freedom is one. The number of available degrees of freedom increases with the addition of side equipment.

The current Degrees of Freedom is one, indicating that only two specifications are active. As noted earlier, a Refluxed Absorber with a partial condenser has two degrees of freedom and, therefore, requires two active specifications. In this case, however, a third degree of freedom was created when the Trim Duty stream was attached as a feed, for which the heat flow is unknown. HYSYS has not made a specification for the third degree of freedom, therefore you need to add a water draw spec called WasteH2O Rate to be the third active specification.

2. Select the **Specs** page. Here you will remove two specifications and add one new specification.
3. In the Column Specifications group, select Reflux Rate and then click the **Delete** button.
4. Delete the Btms Prod Rate specification also.
5. Next you will add the WasteH2O Rate specification. Click the **Add** button. The Add Specs view appears.
6. Select Column Draw Rate and click the **Add Spec(s)** button. The Draw Spec property view appears.
7. In the **Name** cell, type WasteH2O Rate. No further information is required as this specification is de-activated and only estimated when you run the column.

The Draw Spec is entered so that the degrees of freedom is kept at zero throughout this tutorial. It is good practice to keep the degrees of freedom at zero as you modify your column so that you can solve the column after every modification.

**Figure 2.87**






8. Close the view. The new specification appears in the Column Specifications group. The Degrees of Freedom is now zero.
9. Select the **Connections** page. See [Figure 2.86](#).

The Connections page is similar to the first page of the Input Expert. Currently, the column is a standard type, so this page shows a column schematic with the names of the attached streams. When the side equipment is added to the column, the page becomes non-standard. There are a large number of possible non-standard columns based on the types and numbers of side operations that are added. Therefore, HYSYS modifies the Connections page into a tabular format, rather than a schematic format, whenever a column becomes non-standard. In the next section you will add the side equipment and observe how the Connections page is modified.

## Installing the Side Strippers

1. Click the **Side Ops** tab of the Column property view.

**Figure 2.88**




When you install side equipment, it resides in the Column sub-flowsheet. You can build a complex column in the sub-flowsheet while in the Main Flowsheet, the column appears as a single operation. You can then transfer any needed stream information from the sub-flowsheet by simply attaching the stream to the Main Flowsheet.

On this tab, you can Install, View, Edit or Delete all types of Side Equipment. The table displays summary information for a given type of side operation, depending on the page you are currently on.



2. Ensure that you are on the **Side Strippers** page.
3. Click the **Add** button. The Side Stripper view appears.

Figure 2.89




This is a reboiled 3-stage stripper with a 0.75 boil up ratio, so leave the Configuration radio button at Reboiled, and the  $k =$  and Boil Up Ratio fields at their defaults.

4. In the **Name** field, change the name to KeroSS.
5. In the Return Stage drop-down list, select stage 8 (8\_Main TS).
6. In the Draw Stage drop-down list, select stage 9 (9\_Main TS).
7. In the Flow Basis group, select the **Volume** radio button.
8. In the **Product Stream** field, enter Kerosene.

The straight run product distribution data calculated during the Oil Characterization appears in the figure below.

Figure 2.90




The Kerosene liquid volume fraction is 0.129. For 100,000 bbl/day of crude fed to the tower, Kerosene production can be expected at  $100,000 * 0.129 = 12,900$  or approximately 13,000 bbl/day.



9. In the **Draw Spec** field, enter 13000. The completed Side Stripper view appears below.

Figure 2.91



10. Click the **Install** button, and a view summarizing your input appears.
11. Click the **Close** icon to return to the Column property view. Summary information for the new side operation appears in the table on the **Side Ops** tab.



Close icon

Figure 2.92


Side Stripper Summary					
	# Stages	Liq Draw Stage	Vap Return Stage	Outlet Flow [lbmole/hr]	Reboiler Duty [Btu/hr]
KeroSS	3	9_Main TS	8_Main TS	<empty>	<empty>

12. Use the previous steps to install the two remaining side strippers DieselSS and AGOSS. These are both Steam Stripped, so choose the appropriate **Configuration** radio button and create the Steam Feed and Product streams as shown in the following figures. The @COL1 suffix is added automatically.



The completed DieselSS and AGOSS side stripper views appear in the following figure.

Figure 2.93



Although not a requirement, the names of the Steam Feed streams created for these side strippers are identical to the names of the utility steam streams that were created previously in the Main Flowsheet. The conditions of these Steam Feed streams, which reside in the Column sub-flowsheet, are unknown at this point. The conditions of the Main Flowsheet streams are duplicated into these sub-flowsheet streams when the stream attachments are performed.

The completed Side Stripper Summary table appears below.

Figure 2.94

	# Stages	Liq Draw Stage	Vap Return Stage	Outlet Flow [lbmole/hr]	Reboiler Duty [Btu/hr]
KeroSS	3	9_Main TS	8_Main TS	<empty>	<empty>
DieselSS	3	17_Main TS	16_Main TS	<empty>	<empty>
AGOSS	3	22_Main TS	21_Main TS	<empty>	<empty>

13. Click the **Design** tab and select the **Monitor** page.

The Specifications table on this page has a vertical scroll bar, indicating that new specifications have been created below the default ones. Resize the view to examine the entire table.



- Click and drag the bottom border of the view down until the scroll bar disappears, making the entire matrix visible.

Figure 2.95

	Specified Value	Current Value	W/t. Error	Active	Estimate	Current
Distillate Rate	<empty>	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Vap Prod Rate	0.0000 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Reflux Ratio	<empty>	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
WasteH2O Rate	<empty>	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
KeroSS Prod Flow	1300 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
KeroSS BoilUp Ratio	0.7500	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
DieselSS Prod Flow	17000 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
AGOSS Prod Flow	5000 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

View... Add Spec... Group Active Update Inactive Degrees of Freedom 0

The addition of the side strippers has created four more degrees of freedom above the basic column, resulting in a total of seven available degrees of freedom. Currently, however, seven Specifications are Active, so the overall Degrees of Freedom is zero.

The installation of the side strippers created four additional degrees of freedom, so HYSYS created a Prod Flow (product flow) specification for each side stripper, plus a BoilUp Ratio specification for the Kerosene side stripper. The new specifications were automatically made Active to exhaust the four degrees of freedom, returning the overall Degrees of Freedom to 0.


## Installing the Pump Arounds

- Click the **Side Ops** tab and select the **Pump Arounds** page.
- Click the **Add** button. The initial Pump Around view appears.
- In the Return Stage drop-down list, select stage 1 (1\_Main TS).
- In the Draw Stage drop-down list, select stage 2 (2\_Main TS).



- Click the **Install** button, and a more detailed Pump Around view appears.

Figure 2.96




Each cooled pump around circuit has two specifications associated with it. The default Pump Around Specifications are circulation rate and temperature drop (Dt) between the liquid draw and liquid return. For this example, the Dt specification is changed to a Duty specification for the pump around cooler. The pump around rate is 50,000 bbl/day.

1st Active	2nd Active Spec
PA_1_Rate(Pa)	PA_1_Dt(Pa)
5.000e+004 barrel/d	<empty>

- In the empty cell under the PA\_1\_Rate(Pa) specification, enter 5e4.
- Double-click in the blank space under the PA\_1\_Dt(Pa) specification, and the Spec view appears.
- In the **Spec Type** drop-down list, select Duty.
- in the **Spec Value** cell, enter -55e6.

Notice the negative sign convention indicates cooling.


Figure 2.97





10. Click the **Close** icon to return to the Pump Around view.

Figure 2.98



The remainder of the information on the above view is calculated by the Column solver.

11. Click the **Close** icon on the main Pump Around view to return to the Column property view.

12. Repeat the previous steps to install the two remaining pump arounds. Enter Rate specifications of **3e4 barrel/day** and Duty specifications of **-3.5e7 Btu/hr** for both of these pump arounds.

The completed Pump Around views and Liquid Pump Around Summary table appear in the following figures.

Figure 2.99






Figure 2.100

Liquid Pump Around Summary							
	Draw Stage	Return Stage	Flow [lbmole/hr]	Duty [Btu/hr]	Draw T [F]	Return T [F]	Export
PA_1	2_Main TS	1_Main TS	<empty>	-5.500e+007	<empty>	<empty>	<input type="checkbox"/>
PA_2	17_Main TS	16_Main TS	<empty>	-3.500e+007	<empty>	<empty>	<input type="checkbox"/>
PA_3	22_Main TS	21_Main TS	<empty>	-3.500e+007	<empty>	<empty>	<input type="checkbox"/>

13. Click the **Design** tab and select the **Monitor** page. Re-size the property view again so the entire Specifications table is visible.

Figure 2.101

Specifications						
	Specified Value	Current Value	Wt. Error	Active	Estimate	Current
Distillate Rate	<empty>	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Vap Prod Rate	0.0000 barrel/day	<empty>	<empty>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
Reflux Ratio	<empty>	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
WasteH2O Rate	<empty>	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
KeroSS Prod Flow	1300 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
KeroSS BoilUp Ratio	0.7500	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
DieselSS Prod Flow	17000 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
AGOSS Prod Flow	5000 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_1_Rate(Pa)	5.000e+004 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_1_Duty(Pa)	-5.500e+007 Btu/hr	-5.50e+007	0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_2_Rate(Pa)	3.000e+004 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_2_Duty(Pa)	-3.500e+007 Btu/hr	-3.50e+007	0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_3_Rate(Pa)	3.000e+004 barrel/day	<empty>	<empty>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_3_Duty(Pa)	-3.500e+007 Btu/hr	-3.50e+007	0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

View... Add Spec... Group Active Update Inactive Degrees of Freedom 0


The addition of the pump arounds has created six more degrees of freedom, resulting in a total of 13 available degrees of freedom. Currently, 13 Specifications are active, so the overall Degrees of Freedom is zero.

The addition of each pump around created two additional degrees of freedom. As with the side strippers, the specifications for the pump arounds have been added to the list and were automatically activated.



14. Select the **Connections** page.

**Figure 2.102**



The Connections page of a standard refluxed absorber property view is essentially identical to the first page of the refluxed absorber Input Expert, with a column schematic showing the feed and product streams. Side equipment have been added to the standard refluxed absorber, however, making the column non-standard. The Connections page has therefore been modified to show tabular summaries of the Column Flowsheet Topology (i.e., all equipment), Feed Streams and Product Streams.

The column has 40 Total Theoretical Stages:

- 29 in the main tray section
- 1 condenser for the main column
- 9 in the side strippers (3 side strippers with 3 stages each)
- 1 reboiler for the Kerosene side stripper

This topology results in 4 Total Tray Sections—one for the main column and one for each of the three side strippers.



## Completing the Column Connections

When the stream attachments were made on the initial page of the Input Expert, HYSYS automatically created Column sub-flowsheet streams with the same names. For example, when Bottom Steam was attached as a column feed stream, HYSYS created an identical sub-flowsheet stream named Bottom Steam. In the Inlet Streams table on the Connections page, the Main Flowsheet stream is the External Stream, while the sub-flowsheet stream is the Internal Stream.

**Figure 2.103**

Internal Stream	External Stream	Inlet Stage	Transfer Basis	Split
Bottom Steam	Bottom Steam	29_Main TS	P-H Flash	<input type="checkbox"/>
Tower Feed	Tower Feed	28_Main TS	P-H Flash	<input type="checkbox"/>
Trim Duty	Trim Duty	28_Main TS	None Req'd	<input type="checkbox"/>
KeroSS_Energy	<< Stream >>	KeroSS_Reb	None Req'd	<input type="checkbox"/>
Diesel Steam	Diesel Steam	3_DieselSS	P-H Flash	<input type="checkbox"/>
AGO Steam	AGO Steam	3_AGOSS	P-H Flash	<input type="checkbox"/>

If you scroll down the list of Inlet Streams, notice that the two side stripper steam streams, DieselSteam and AGOSteam, are Internal and External, meaning that these streams are attached to the Main Flowsheet streams that were created earlier.

For the purposes of this tutorial, it is not required to export the pump around duty streams **PA\_1\_Q**, **PA\_2\_Q** and **PA\_3\_Q** to the Main Flowsheet, so their **External Stream** cells remain undefined.

## Adding Column Specifications

Select the Monitor page of the Column property view.

The current Degrees of Freedom is zero, indicating the column is ready to be run. Before you run the column, however, you will have to replace two of the active specifications, Waste H2O Rate and KeroSS BoilUp Ratio, with the following new ones:



- Overflash specification for the feed stage (Tray Net Liquid Flow specification)
- Kerosene side stripper reboiler duty specification



## Adding the Overflash Specification

1. On the **Design** tab, move to the **Specs** page.

Figure 2.104




2. In the Column Specifications group, click the **Add** button. The Column Specifications view appears.
3. Select Column Liquid Flow as the Column Specification Type.
4. Click the **Add Spec(s)** button, and the Liq Flow Spec view appears.
5. Change the name from its default to Overflash.
6. In the **Stage** cell, select 27\_Main TS from the drop-down list of available stages.

A typical range for the Overflash rate is 3-5% of the total feed to the column. In this case, the total feed rate is 100,000 barrels/day. For the Overflash specification 3.5%, or 3,500 barrels/day is used.



7. In the **Spec Value** cell, enter 3500.

Figure 2.105




8. Close the view to return to the Column property view. The new specification appears in the list of Column Specifications group on the **Specs** page.

## Adding the Duty Specification

9. Click the **Add** button again to add the second new specification.
10. Select Column Duty as the Column Specification Type, then click the **Add Spec(s)** button. The Duty Spec view appears.
11. In the **Name** cell, change the name to Kero Reb Duty.
12. In the **Energy Stream** cell, select KeroSS\_Energy @COL1 from the drop-down list.
13. In the **Spec Value** cell, enter 7.5e6 (Btu/hr).


Figure 2.106





- Close the view to return to the **Specs** page of the Column property view. The completed list of Column Specifications is shown in the figure below

Figure 2.107



## Running the Column

- Select the **Monitor** page to view the Specifications matrix.

The Degrees of Freedom is again zero, so the column is ready to be calculated, however, a value for the distillate (Naphtha) rate specification must be supplied initially. In addition, there are some specifications which are currently Active that you want to use as Estimates only, and vice versa.

Make the following final changes to the specifications:

- In the **Specified Value** cell for the Distillate Rate specification, enter 2e4 (bbl/day).
- Activate the Overflash specification by clicking its **Active** checkbox.
- Activate the Kero Reb Duty specification.
- Activate the Vapour Prod Rate specification.
- Deactivate the Reflux Ratio specification.
- Deactivate the Waste H2O Rate specification.
- Deactivate the KeroSS BoilUp Ratio specification.

If the column begins to run on its own before you click the **Run** button, click the **Stop** button and continue activating or deactivating specifications.




- Click the **Run** button to begin calculations. The information displayed on the page is updated with each iteration. The column converges as shown in the figure below.

Figure 2.108

This matrix displays the Iteration number, Step size, Equilibrium error and Heat/Spec error.

The column temperature profile is shown here. You can view the pressure or flow profiles by picking the appropriate radio button.



The status indicator has changed from Unconverged to Converged.


The converged temperature profile is currently displayed in the upper right corner of the view. To view the pressure or flow profiles, select the appropriate radio button.

In the Performance tab, the Column Profiles and Feed/Products pages display more detailed stage summary. In the Basis group near the top of the view, select the Liq Vol radio button to examine the tray vapour and liquid flows on a volumetric basis.



The Column Profiles page appears below.

Figure 2.109






## Viewing Boiling Point Profiles for the Product Stream

You can view boiling point curves for all the product streams on a single graph:


1. On the **Performance** tab, click on the **Plots** page.

Figure 2.110



2. In the Refinery Assay Curves group, select Boiling Point Assay.
3. Click the **View Graph** button, and the Boiling Point Properties view appears.


Figure 2.111





- Click the **Profile Data Control** button, and the Data Control view appears as shown below.

Figure 2.112



You can view boiling point properties of a single tray or multiple trays. The boiling point properties of all stages, from which products are drawn, are important for this Tutorial.

- Select the **Multi Tray** radio button in the Style group. The Data Control view is modified, showing a matrix of column stages with a checkbox for each stage.
- Activate the following stages by clicking on their blank checkboxes:
  - Condenser (Naphtha product stage)
  - 29\_Main TS (Residue)
  - KeroSS\_Reb (Kerosene)
  - 3\_DieselSS (Diesel)
  - 3\_AGOSS (AGO)

The TBP profile for the light liquid phase on each stage can be viewed, on a liquid volume basis.


- Select TBP in the drop-down list under the tray matrix in the Style group.
- In the Basis group, select the **Liquid Vol** radio button.
- Activate the **Light Liquid** checkbox in the phase group to activate it.
- Leave the Visible Points at its default setting of 15 Points. You can display more data points for the curves by selecting the 31 Points radio button.




The completed Data Control view is shown below.

The independent (x-axis) variable is the Assay Volume Percent, while the dependent (y-axis) variable is the TBP in °C.

Figure 2.113




11. Click on the **Close** icon  to close the Data Control view. You return to the Boiling Point Properties view, which now displays the TBP curves.
12. Make the Boiling Point Properties view more readable by clicking the **Maximize** icon in the upper right corner of the view, or by clicking and dragging its border to a new view size.

The Boiling Point Properties view is shown below.

Figure 2.114

Move the graph legend by double-clicking inside the plot area, then click and drag the legend to its new location.



13. When you are finished viewing the profiles, click the **Close** icon.



PFD icon



Workbook icon




Column Runner icon

1. Click the **Column Environment** button at the bottom of the column property view.
2. While inside the column environment, you might want to:
  - view the Column sub-flowsheet PFD by clicking the **PFD** icon.
  - view a Workbook of the Column sub-flowsheet objects by clicking the **Workbook** icon.
  - access the "inside" column property view by clicking the **Column Runner** icon. This property view is essentially the same as the "outside", or Main Flowsheet, property view of the column.

The Column sub-flowsheet PFD is shown below.

**Figure 2.115**





## Customizing the Column PFD

You can customize the PFD shown above by re-sizing the column and "hiding" some of the column trays to improve the overall readability of the PFD. To hide some of the trays in the main column:



Maximize icon




Zoom All icon



Object Inspect menu

1. Click the **PFD** icon to ensure the column PFD is active.
2. Click the **Maximize** icon in the upper right corner of the PFD view to make it full-screen.
3. Click the **Zoom All** icon at the bottom left of the PFD view to fill the re-sized PFD view.
4. Object inspect (right-click) the main column tray section, and the object inspection menu appears.
5. Select **Show Trays** from the object inspection menu. The Stage Visibility view appears.
6. Select the **Selected Expansion** radio button.
7. Hide stages 4, 5, 6, 11, 12, 13, 14, 24, 25 and 26 by deactivating their **Shown** checkboxes.

Figure 2.116



8. Click the **Close** icon on the Stage Visibility view to return to the PFD. The routing of some streams in the **PFD** can be undesirable. You can improve the stream routing by completing the next step.
9. From the **PFD** menu item, select **Auto Position**, and HYSYS rearranges the PFD in a logical manner.




## Enlarge Icon

The next task in customizing the PFD is to enlarge the icon for the main column:



Size icon




1. Click on the icon for the main tray section (Main TS).
2. Click the **Size** icon on the PFD button bar, and a frame with eight sizing handles appears around the tray section icon.
3. Place the cursor over the handle at the middle right of the icon, and the cursor changes to a double-ended sizing arrow.
4. With the sizing cursor visible, click and drag to the right. An outline appears, showing what the new icon size is when you complete the next step.
5. When the outline indicates a new icon size of about 1.5 to 2 times the width of the original size, release the button. The tray section icon is now re-sized.
6. Click the **Size** icon again to return to **Move** mode.

The final task is to customize the PFD by moving some of the streams and operation labels (names) so they do not overlap. To move a label:

7. Click on the label you want to move.
8. Right-click and select **Move/Size Label**.
9. Move the label to its new position by clicking and dragging it, or by pressing the arrow keys.

You can also move the icon on its own simply by clicking and dragging it to the new location.


10. When you are finished working with the maximized Column PFD, click the **Restore** icon  for the **PFD** (not for the HYSYS Application view) in the upper right corner of the view of the PFD. The PFD returns to its previous size.
11. You can manually resize the view, and expand the PFD to fill the new size by again clicking the **Zoom All** icon in the lower left corner of the PFD view.

For more information on customizing the PFD, refer to [Chapter 7.25 - PFD](#) in the User Guide.



The customized PFD appears below.

Figure 2.117



12. To view the workbook for the column, click the **Workbook** icon.

Figure 2.118

Workbook - Atmos Tower (COL1)							
Name	Reflex	To Condenser	Residue	Naphtha	Off Gas	Bottom Steam	Tower Feed
Vapour Fraction	0.0000	1.0000	0.0000	0.0000	1.0000	1.0000	0.6040
Temperature [F]	165.3	267.1	657.2	165.3	165.3	375.0	641.6
Pressure [psia]	19.70	28.70	32.70	19.70	19.70	150.0	65.00
Molar Flow [lbmole/hr]	1153	5701	882.8	1491	1.002e+004	416.3	3814
Mass Flow [lb/hr]	1.563e+005	4.135e+005	5.535e+005	2.021e+005	6.769e+003	7500	1.144e+006
Liquid Volume Flow [barrel/day]	1.546e+004	3.924e+004	4.503e+004	2.000e+004	7.122e+004	514.6	1.000e+005
Heat Flow [Btu/hr]	-1.356e+008	-5.664e+008	-2.839e+008	-1.754e+008	-7.852	-4.222e+007	-5.787e+008
Name	WasteH2O	KeroSS_Draw	KeroSS_Return	Kerosene	KeroSS_BoilUp	KeroSS_ToReb	AGOSS_Draw
Vapour Fraction	0.0000	0.0000	1.0000	0.0000	1.0000	0.0000	0.0000
Temperature [F]	165.3	397.5	418.8	450.3	450.3	439.0	600.9
Pressure [psia]	19.70	29.84	29.84	29.84	29.84	29.84	31.70
Molar Flow [lbmole/hr]	3058	746.3	79.56	666.7	355.2	1022	428.9
Mass Flow [lb/hr]	5.508e+004	1.549e+005	1.374e+004	1.412e+005	7.109e+004	2.123e+005	1.518e+005
Liquid Volume Flow [barrel/day]	3779	1.429e+004	1294	1.300e+004	6595	1.960e+004	1.333e+004
Heat Flow [Btu/hr]	-3.702e+008	-1.126e+008	-8.845e+006	-9.624e+007	-4.263e+007	-1.464e+008	-8.532e+007
Name	AGOSS_Return	AGO	AGO Steam	DieselSS_Draw	DieselSS_Return	Diesel	Diesel Steam
Vapour Fraction	1.0000	0.0000	1.0000	0.0000	1.0000	0.0000	1.0000
Temperature [F]	537.6	415.8	300.0	485.9	482.1	467.3	300.0
Pressure [psia]	31.70	31.70	50.00	30.99	30.99	30.99	50.00
Molar Flow [lbmole/hr]	2795	143.7	2500	781.4	292.8	655.1	166.5
Mass Flow [lb/hr]	1.393e+005	5.759e+004	4.504e+004	2.196e+005	3.239e+004	1.902e+005	3000
Liquid Volume Flow [barrel/day]	1.142e+004	5001	3090	1.969e+004	2897	1.700e+004	205.8
Heat Flow [Btu/hr]	-2.997e+008	-4.034e+007	-2.547e+008	-1.436e+008	-3.348e+007	-1.271e+008	-1.697e+007
Name	PA_1_Draw	PA_1_Return	PA_2_Draw	PA_2_Return	PA_3_Draw	PA_3_Return	
Vapour Fraction	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	
Temperature [F]	311.2	126.6	485.9	331.8	600.9	465.3	
Pressure [psia]	28.84	28.84	30.99	30.99	31.70	31.70	
Molar Flow [lbmole/hr]	3048	3048	1191	1191	965.2	965.2	
Mass Flow [lb/hr]	5.282e+005	5.282e+005	3.345e+005	3.345e+005	3.417e+005	3.417e+005	
Liquid Volume Flow [barrel/day]	5.000e+004	5.000e+004	3.000e+004	3.000e+004	3.001e+004	3.001e+004	
Heat Flow [Btu/hr]	-4.100e+008	-4.650e+008	-2.188e+008	-2.538e+008	-1.920e+008	-2.270e+008	






Enter Parent Simulation  
Environment icon

The PFD shown in the [Figure 2.119](#) has been manually rearranged by moving some of the stream icons, and by enlarging the furnace icon.

- When you are finished working in the Column environment, return to the Main Flowsheet by clicking the **Enter Parent Simulation Environment** icon.
- Open the PFD for the Main Flowsheet, then select **Auto Position All** from the **PFD** menu item. HYSYS arranges the Main Flowsheet PFD in a logical manner according to the layout of the flowsheet.

Figure 2.119



## 2.2.9 Viewing and Analyzing Results

- Open the Workbook to access the calculated results for the Main Flowsheet. The Material Streams tab of the Workbook appears below.

Figure 2.120

Workbook - Case (Main)									
Name	Preheat Crude	Bottom Steam	Diesel Steam	AGO Steam	PreFlashVap	PreFlashLiq	Hot Crude	Tower Feed	
Vapour Fraction	0.1003	1.0000	1.0000	1.0000	1.0000	0.0000	0.5478	0.6040	
Temperature [F]	450.0	375.0	300.0	300.0	450.0	450.0	650.0	641.6	
Pressure [psia]	75.00	150.0	50.00	50.00	75.00	75.00	65.00	65.00	
Molar Flow [lbmole/hr]	3814	416.3	166.5	2500	382.4	3431	3431	3814	
Mass Flow [lb/hr]	1.144e+006	7500	3000	4.504e+004	4.958e+004	1.095e+006	1.095e+006	1.144e+006	
Liquid Volume Flow [barrel/day]	1.000e+005	514.6	205.8	3090	4941	9.506e+004	9.506e+004	1.000e+005	
Heat Flow [Btu/hr]	-7.650e+008	-4.222e+007	-1.697e+007	-2.547e+008	-3.034e+007	-7.346e+008	-5.484e+008	-5.787e+008	
Name	Off Gas	Naphtha	WasteH2O	Residue	Kerosene	AGO	Diesel	*** New ***	
Vapour Fraction	1.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000		
Temperature [F]	165.3	165.3	165.3	657.2	450.3	415.8	467.3		
Pressure [psia]	19.70	19.70	19.70	32.70	29.84	31.70	30.99		
Molar Flow [lbmole/hr]	1.002e-004	1491	3058	882.8	666.7	143.7	655.1		
Mass Flow [lb/hr]	6.769e-003	2.021e+005	5.508e+004	5.535e+005	1.412e+005	5.759e+004	1.902e+005		
Liquid Volume Flow [barrel/day]	7.122e-004	2.000e+004	3779	4.503e+004	1.300e+004	5001	1.700e+004		
Heat Flow [Btu/hr]	-7.852	-1.754e+008	-3.702e+008	-2.839e+008	-9.624e+007	-4.034e+007	-1.271e+008		
Material Streams									
FeederBlock_Preheat Cr PreFlash									
<input type="checkbox"/> Include Sub-Flowsheets <input type="checkbox"/> Show Name Only Number of Hidden Objects: 0									



## Using the Object Navigator

Now that results have been obtained, you can view the calculated properties of a particular stream or operation. The Object Navigator allows you to quickly access the property view for any stream or unit operation at any time during the simulation.


1. Open the Navigator by doing **one** of the following:
  - Press **F3**.
  - From the **Flowsheet** menu, select **Find Object**.
  - Double-click on any blank space on the HYSYS Desktop.
  - Click the **Object Navigator** icon.



Object Navigator icon

The Object Navigator view appears:

Figure 2.121



The UnitOps radio button in the Filter group is currently selected, so only the Unit Operations appear in the list of objects. To open a property view, select the operation in the list, and click the View button, or double-click on the operation. You can change which objects appear by selecting a different Filter radio button. For example, to list all streams and unit operations, select the All radio button.

You can start or end the search string with an asterisk (\*), which acts as a wildcard character. This lets you find multiple objects with one search. For example, searching for VLV\* will open the property view for all objects with VLV at the beginning of their name.

You can also search for an object by clicking the Find button. When the Find Object view appears, enter the Object Name, and click the OK button. HYSYS opens the property view for the object whose name you entered.




## 2.2.10 Installing a Boiling Point Curves Utility

Previously, the boiling point profiles for the product streams was viewed using the Plots page in the column property view. You can also view boiling point curves for a product stream using HYSYS' BP Curves Utility. To create a Boiling Point curves utility for the Kerosene product:

1. Open the Navigator using one of the methods described above.
2. Select the **Streams** radio button.
3. Scroll down the list of Streams and select Kerosene.
4. Click the **View** button, and the property view for stream Kerosene appears.
5. On the **Attachments** tab, move to the **Utilities** page of the stream property view.
6. Click the **Create** button. The Available Utilities view appears, presenting you with a list of HYSYS utilities.

Figure 2.122




7. Find BP Curves and do **one** of the following:
  - Select BP Curves, then click the **Add Utility** button.
  - Double-click on BP Curves.
8. HYSYS creates the utility and opens the BP Curves view.
9. On the Design tab, go to the **Connections** page. Change the name of the utility from the default Boiling Point Curves-1 to Kerosene BP Curves.



A Utility is a separate entity from the stream it is attached to; if you delete it, the stream is not affected. Likewise, if you delete the stream, the Utility remains but cannot display any information until you attach another stream using the Select Object button.


10. Change the curve basis to Liquid Volume by selecting it in the Basis drop-down list.

Figure 2.123



11. You can scroll through the matrix of data to see that the TBP ranges from 267°F to 498°F by going to the Performance tab and selecting Results page.


Figure 2.124






This boiling range predicted by the utility is slightly wider than the ideal range calculated during the Oil characterization procedure for Kerosene, 356°F to 464°F.

Figure 2.125



12. Select the **Plots** page on the **Parameters** tab of the utility property view to view the data in graphical format.

Figure 2.126



To make the envelope more readable, maximize or resize the view.

13. When you move to the Plots view, the graph legend can overlap the plotted data. To move the legend, double-click anywhere in the plot area then click and drag the legend to its new location.
14. When you are finished viewing the Boiling Point Curves, click the **Close** icon.




## Installing a Second Boiling Point Curves Utility

Alternative to using the Utilities page of a stream property view, you can also install a utility using the Available Utilities view. Another BP Curves utility is installed for stream Residue. This utility is used for the case study in the next section. To install the utility:

1. Do one of the following:
  - press **CTRL U**.
  - from the **Tools** menu, select **Utilities**.

The Available Utilities view appears.


Figure 2.127



Notice the name of the utility created previously, Kerosene BP Curves, appears in the Available Utilities view.

2. Select Boiling Point Curves, and click the **Add Utility** button. The Boiling Point Curves view appears, opened to the **Design** tab.


Figure 2.128






3. Change the name from its default Utility-1 to Residue BP Curves.
4. Change the Basis to Liquid Volume by selecting it in the drop-down list. The next task is to attach the utility to a material stream.
5. Click the **Select Object** button, and the Select Process Stream view appears.

Figure 2.129



6. Select Residue in the Object list, then click the **OK** button. HYSYS calculates the boiling point curves. The completed **Performance** tab appears below.

Figure 2.130



Notice that the stream name Residue now appears in the Stream cell.

7. Click the **Close** icon on the Residue BP Curves view, and then on the Available Utilities view.




## 2.2.11 Using the Databook

The HYSYS Databook provides you with a convenient way to examine your flowsheet in more detail. You can use the Databook to monitor key variables under a variety of process scenarios, and view the results in a tabular or graphical format. To open the Databook, do **one** of the following:

- press **CTRL D**.
- from the **Tools** menu, select **Databook**.

The Databook appears below.

Figure 2.131



## Adding Variables to Databook

The first step is to add the key variables to the Databook using the Variables tab. For this example, the Overflash specification is varied and examined to investigate its effect on the following variables:


- D1160 Boiling Temperature for 5% volume cut point of stream Residue
  - heat flow of energy stream TrimDuty
  - column reflux ratio
1. Click the **Insert** button, and the Variable Navigator view appears.
  2. Select the **UnitOps** radio button in the Object Filter group. The Object list is filtered to show unit operations only.
  3. Select Atmos Tower in the Object list, and the Variable list available for the column appears to the right of the Object list.



The Variable Navigator is used extensively in HYSYS for locating and selecting variables. The Navigator operates in a left-to-right manner—the selected Flowsheet determines the Object list, the chosen Object dictates the Variable list, and the selected Variable determines whether any Variable Specifics are available.

4. Select Reflux Ratio in the Variable list.


Figure 2.132



HYSYS duplicates this variable name in the Variable Description field. If you want, you can edit the default description. To edit the default description:

5. Click inside the Variable Description field and delete the default name.
6. Type a new description, such as Reflux Ratio, and click the OK button. The variable now appears in the Databook.

Figure 2.133




7. To add the next variable, click the **Insert** button, and the Variable Navigator again appears.
8. Select the **Streams** radio button in the Object Filter group. The Object list is filtered to show streams only.



9. Scroll down and click on Trim Duty in the Object list, and the Variable list available for energy streams appears to the right of the Object list.
10. Select Heat Flow in the Variable list.
11. In the **Variable Description** field, change the description to Trim Duty, and click the **OK** button. The variable now appears in the Databook.

Figure 2.134




12. Click the **Insert** button again to add the third variable, the ASTM D1160 cut point from the Residue BP Curves utility.
13. Select the **Utility** radio button in the Navigator Scope group.
14. Select Residue BP Curves in the Object list.
15. Select ASTM D1160 - Vac in the Variable list.
16. Select the fifth item listed in the Variable Specifics column. This corresponds to the 5% volume cut point.




17. In the Variable Description field, change the variable name to ASTM 1160 - Vac 5% Residue, and click the OK button.

Figure 2.135



18. The completed Variables tab of the Databook appears below.

Figure 2.136






## Create a Data Table

Now that the key variables to the Databook have been added, the next task is to create a data table to display those variables:

1. Click on the **Process Data Tables** tab.
2. Click the **Add** button in the Available Process Data Tables group. HYSYS creates a new table with the default name ProcData1.

Figure 2.137




3. Change the default name from ProcData1 to Key Variables by editing the **Process Data Table** field.

Notice that the three variables added to the Databook appear in the matrix on this tab.

4. Activate each variable by clicking on the corresponding **Show** checkbox.


Figure 2.138





- Click the **View** button to view the new data table, which is shown below.

Figure 2.139



Object	Variable	Value	Units
Atmos Tower	Reflux Ratio	0.7720	
Trim Duty	Trim Duty	3.179e+007	Btu/hr
Residue BP Cur	ASTM 1160 - Vac 5% Resi	389.6	F

View DataBook...

This table is accessed later to demonstrate how its results are updated whenever a flowsheet change is made.

- For now, click the **Minimize** icon in the upper right corner of the Key Variables Data view. HYSYS reduces the view to an icon and places it at the bottom of the Desktop.

## Recording Data

Suppose you now want to make changes to the flowsheet, but you would like to record the current values of the key variables before making any changes. Instead of manually recording the variables, you can use the Data Recorder to automatically record them for you. To record the current values:

- Click on the **Data Recorder** tab.

Figure 2.140

Figure 2.140

The screenshot shows the 'DataBook' application window. The 'Data Recorder' tab is selected at the bottom. The window is divided into several sections:

- Available Scenarios:** A list box on the left is empty. To its right are three buttons: 'Record...', 'Add', and 'Delete'.
- Available Display:** Two radio buttons are present: 'Table' (selected) and 'Graph'. To their right is a 'View...' button.
- Data Recorder Data Selection:** This section contains a 'Current Scenario' text field and a table.

Object	Variable	Include
Atmos Tower	Reflux Ratio	<input checked="" type="checkbox"/>
Trim Duty	Trim Duty	<input checked="" type="checkbox"/>
Residue BP Cur	ASTM 1160 - Vac 5% Residue	<input checked="" type="checkbox"/>


At the bottom of the window, there is a row of tabs: 'Variables', 'Process Data Tables', 'Strip Charts', 'Data Recorder' (active), and 'Case Studies'.



When using the Data Recorder, you first create a Scenario containing one or more of the key variables, then record the variables in their current state.

2. Click the **Add** button in the Available Scenarios group, and HYSYS creates a new scenario with the default name Scenario 1. It is required to include all three key variables in this scenario.
3. Activate each variable by clicking on the corresponding **Include** checkbox.

**Figure 2.141**



4. Click the **Record** button to record the variables in their current state. The New Solved State view appears, prompting you for the name of the new state.
5. Change the **Name for New State** from the default State 1 to 3500 O.F. (denoting 3500 bbl/day Overflash). Click the **OK** button, and you return to the Databook.
6. In the Available Display group, select the **Table** radio button.




**Figure 2.142**



7. Double-click on the **Key Variables Data** icon to restore the view to its full size. The updated key variables are shown below.

Figure 2.143




Object	Variable	Value	Units
Atmos Tower	Reflux Ratio	0.5858	
Trim Duty	Trim Duty	1.883e+007	Btu/hr
Residue BP Cur	ASTM 1160 - Vac 5% Resi	377.8	F

View DataBook...

As a result of the change:

- the Trim Duty has decreased
  - the Residue D1160 Vacuum Temperature 5% cut point has decreased
  - the column reflux ratio has decreased
8. Press **CTRL D** to make the Databook active again. You can now record the key variables in their new state.
  9. Move to the **Data Recorder** tab in the Databook.
  10. Click the **Record** button, and HYSYS provides you with the default name State 2 for the new state.
  11. Change the name to 1500 O.F., and click the **OK** button to accept the new name.
  12. Click the **View** button and the Data Recorder appears, displaying the new values of the variables.


Figure 2.144



State		
3500 O.F.		1500 O.F.
Reflux Ratio	0.7722	0.5857
Trim Duty [Btu/hr]	3.172e+007	1.883e+007
ASTM 1160 - Vac 5%	389.5	377.8



13. Record the process variables for **Overflash** rates of 5500 and 7500 barrels/day. Enter names for these variable states of 5500 O.F. and 7500 O.F., respectively. The final Data Recorder appears below.

**Figure 2.145**




## 2.3 Dynamic Simulation

This complete dynamic case has been pre-built and is located in the file **DynTUT2.hsc** in your HYSYS\Samples directory.

In this tutorial, the dynamic capabilities of HYSYS are incorporated into a basic steady state oil refining model. A simple fractionation facility produces naphtha, kerosene, diesel, atmospheric gas oil, and atmospheric residue products from a heavy crude feed. In the steady state refining tutorial, preheated crude was fed into a pre-flash drum which separated the liquid crude from the vapour. The liquid crude was heated in a furnace and recombined with the vapour. The combined stream was then fed to the atmospheric crude column for fractionation. The dynamic refining tutorial only considers the crude column. That is, the crude preheat train is deleted from the flowsheet and only the crude column in the steady state refining tutorial is converted to dynamics.

Figure 2.146



The main purpose of this tutorial is to provide you with adequate knowledge in converting an existing steady state column to a dynamics column. The tutorial provides a single way of preparing a steady state case for dynamics mode, however, you can also choose to use the Dynamic Assistant to set pressure specifications, size the equipment in the plant, and/or add additional equipment to the simulation flowsheet.



In this tutorial, you follow this basic procedure in building the dynamic model.

This tutorial comprehensively guides you through the steps required to add dynamic functionality to a steady state oil refinery simulation. To help navigate these detailed procedures, the following milestones have been established for this tutorial.

1. Obtain a simplified steady state model to be converted to dynamics.
2. Implement a tray sizing utility for sizing the column and the side stripper tray sections.
3. Install and define the appropriate controllers.
4. Add the appropriate pressure-flow specifications.
5. Set up the Databook. Make changes to key variables in the process and observe the dynamic behaviour of the model.

## 2.3.1 Simplifying the Steady State Flowsheet


In this section, you will The preflash train in the steady state simulation case R-1.hsc is deleted in this section:

1. Open the pre-built case file **R-1.hsc**. The crude column simulation file R-1.hsc is located in your HYSYS\Samples directory.
2. Press F4 to make the Object Palette visible.


For the purpose of this example, the Session Preferences are set so that the Dynamic Assistant will not manipulate the dynamic specifications.

3. From the **Tools** menu, select **Preferences**. The Session Preference view appears.
4. On the **Simulation** tab, select the **Dynamics** page.
5. Deactivate the **Set dynamic stream specifications in the background** checkbox.

Figure 2.147




In this tutorial, you are working with SI units. The units are changed by entering the Preferences property view in the Tools menu bar. In the Units tab, specify SI in the Current Unit Set group.

6. Click the **Variables** tab, then select the **Units** page.
7. In the Available Unit Sets group, select SI.
8. Click the **Close** icon  to close the Session Preferences view. Close all other views except for the PFD view.



9. Add a material stream to the PFD by doing one of the following:
  - From the **Flowsheet** menu, select **Add Stream**.
  - Double-click the **Material Stream** icon on the Object Palette.
10. In the **Stream Name** cell, type Store. This stream will be used to store information from the Atm Feed stream.

Figure 2.148




11. In the Store stream property view, click the **Define from other Stream** button. The Spec Stream As view appears.




12. In the Available Streams group, select **Atm Feed**.

Figure 2.149



13. Click on the **OK** button to copy the **Atm Feed** stream information to the **Store** stream.

Figure 2.150



14. Close the **Store** stream view.



When you delete a stream, unit or logical operation from the flowsheet, HYSYS asks you to confirm the deletion. If you want to delete the object, click the Yes button. If not, click the No button.


15. Delete all material streams and unit operations upstream of the Atm Feed stream. The following eight items should be deleted:

Items to be deleted		
Material Streams	Energy Streams	Unit Operations
Hot Crude Pre Flsh Liq Pre Flsh Vap Raw Crude	Crude Duty	Pre Flash Separator Crude Heater Mixer

After you delete the above items, stream Atm Feed is not fully specified.

16. Double-click the Atm Feed stream icon to open its property view.
17. Click the **Define from other Stream** button. The Spec Stream As property view appears.
18. In the Available Streams group, select Store, then click **OK**.

Figure 2.151



19. Close the Atm Feed stream view, then delete the stream Store.

Make sure that the **Standard Windows file picker** radio button is selected on the **File** page in the Session Preferences view. For more information on Session Preferences please refer to [Chapter 12.5 - Files Tab](#) in the User Manual.

This steady state case now contains the crude column without the preflash train. Since the identical stream information was copied to stream Atm Feed, the crude column operates the same as before the deletion of the preflash train.

20. Save the case as **DynTUT2-1.hsc**.



## 2.3.2 Adding Equipment & Sizing Columns


In preparation for dynamic operation, the column and side stripper tray sections and surrounding equipment must be sized. In the steady state scenario, column pressure drop is user specified. In dynamics, it is calculated using dynamic hydraulic calculations. Complications arise in the transition from steady state to dynamics if the steady state pressure profile across the column is very different from that calculated by the Dynamic Pressure-Flow solver.

The Cooler operations in the pump arounds are not specified with the Pressure Flow or Delta P option, however, each cooler must be specified with a volume in order to run properly in dynamic mode.

### Column Tray Sizing

1. Open the Utilities property view by pressing CTRL U. The Available Utilities view appears.
2. Scroll down the list of available utilities until the Tray Sizing utility is visible.


Figure 2.152






3. Select Tray Sizing, then click the **Add Utility** button. The Tray Sizing view appears.

Figure 2.153



4. In the **Name** field, change the name to Main TS.
5. Click the **Select TS** button. The Select Tray Section view appears.

Figure 2.154




6. In the Flowsheet list, select T-100, then select Main TS in the Object list. Click the **OK** button.
7. In the Use Tray Vapour to Size drop-down list, select Always Yes.



8. Click the **AutoSection** button. The AutoSection view appears. The default tray internal types appear as follows:

Figure 2.155



**Auto Section Information**

Internal Type  
☐ Sieve ☒ Valve ☐ Bubble Cap ☐ Packed

Area Tolerance  
 When the ratio between the current calc'd area and either of min/max previous areas for the section exceeds this tolerance, a new diameter section is started.  
 Higher more sections; lower fewer sections.


NFP Diam Factor  
 When a new number of flow paths will result in a diameter diff  $\geq$  diam fact \* old diameter, a new NFP section is started.  
 Not required for packed columns.  
 Lower more sections; higher fewer sections.

Cancel Next >

The Valve tray type is selected as the default option. This option is entered into the Main TS property view.

9. Keep the default values and click **Next**. The next view displays the specific dimensions of the valve-type trays.
10. Keep the default values and click the **Complete AutoSection** button.

Figure 2.156



**Tray Section Information**

Internals  
☐ Sieve ☒ Valve ☐ Bubble ☐ Packed

Valve Tray

Orifice Type	Straight
Design Manual	Glitsch
Valve Matl Density	8220 kg/m <sup>3</sup>
Valve Matl Thickness	1.524 mm
Hole Area (% of AA)	15.30 %

Common Tray Properties

Tray Spacing	609.6 mm
Tray Thickness	3.175 mm
Tray Foaming Factor	1.000
Max Tray dP (ht of liquid)	152.4 mm
Max Tray Flooding	85.00 %

DC/Weir Info

Weir Height	50.80 mm
Max Weir Loading	89.42 m <sup>3</sup> /h-m
Downcomer Type	Vertical
Downcomer Clearance	38.10 mm
Maximum DC Backup	50.00 %

Delete Complete AutoSection



HYSYS calculates the Main TS tray sizing parameters based on the steady state flow conditions of the column and the desired tray types.

Two tray section sizes, Section\_1 and Section\_2, appear in the Setup page of the Design tab. Section\_1 includes trays 1 to 27; Section\_2 includes trays 28 and 29. Since there are different volumetric flow conditions at each of these sections, two different tray section types are necessary.

**Figure 2.157**

Section Name	Section_1	Section_2
Start	1_Main TS	28_Main TS
End	27_Main TS	29_Main TS
Internals	Valve	Valve
Mode	Design	Design
Active	<input type="checkbox"/>	<input type="checkbox"/>
Status	Complete	Complete
Design Limit	DC Backup	Weir Loading
Limiting Stage	1_Main TS	28_Main TS

11. Click the **Design** tab, then select the **Specs** page.
12. In the **Number of Flow Paths** cell, enter 3 for both Section\_1 and Section\_2.
13. Click the **Performance** tab, then select the **Results** page to see the dimensions and configuration of the trays for Section\_1 and Section\_2. Since Section\_1 is sized as having the largest tray diameter, its tray section parameters should be recorded.
14. Confirm the following tray section parameters for Section\_1.

Variable	Value
<b>Section Diameter</b>	5.639 m
<b>Weir Height</b>	0.0508 m
<b>Tray Spacing</b>	0.6096 m
<b>Total Weir Length</b>	13.31 m

The number of flow paths for the vapour is 3. The Actual Weir length is therefore the Total Weir Length recorded/3.

15. Calculate the Actual Weir length:

Variable	Value
<b>Actual Weir Length (Total Weir Length/3)</b>	4.44 m



16. Confirm the Maximum Pressure Drop/Tray and check the number of trays in the Main TS column. The Total Section Pressure drop is calculated by multiplying the number of trays by the Maximum Pressure Drop/Tray.

Variable	Value
Maximum Pressure Drop/Tray	0.831 kPa
Number of Trays	29
Section DeltaP	24.10 kPa

17. Close the Tray Sizing: Main TS and Available Utilities views.
18. Double-click on the Column T-100 icon in the PFD, then click the **Column Environment** button to enter the Column subflowsheet.
19. On the column PFD, double-click the Main TS Column icon to enter the Main TS property view.
20. Click the **Rating** tab, then select the **Sizing** page.
21. Enter the previous calculated values into the following tray section parameters:
- Diameter 5.639m
  - Tray Spacing 0.6096m
  - Weir Height 0.0508m
  - Weir Length (Actual Weir Length) 4.44m
22. In the Internal Type group, select the **Valve** radio button.

Be aware that the default units for each tray section parameter may not be consistent with the units provided in the tray sizing utility. You can select the units you want from the drop-down list that appears beside each input cell.

Figure 2.158

The screenshot shows the 'Main TS' window with the 'Rating' tab selected. Under the 'Rating' tab, the 'Sizing' sub-tab is active. The 'Tray Dimensions' section contains the following parameters and values:

Tray Space [m]	0.6096
Tray Vol [m3]	15.22
Diameter [m]	5.639
Weir Height [m]	5.080e-002
Weir Length [m]	4.440
DC Volume [m3]	8.836e-002
Active Area [m2]	<empty>
Flow Paths	1

Below the 'Tray Dimensions' section is the 'Internal Type' group with four radio buttons: Sieve, Valve (selected), Bubble Cap, and Packed. A 'Quick Size' button is located to the right of the 'Internal Type' group. At the bottom of the window, there are tabs for 'Design', 'Rating' (active), 'Worksheet', 'Performance', and 'Dynamics'. Below the tabs are three buttons: 'Delete', 'OK' (highlighted in green), and 'Ignored'.






Column Runner icon

23. Close the Main TS property view.
24. Access the Column property view by clicking the **Column Runner** icon in the tool bar.
25. Click the **Parameters** tab, then select the **Profiles** page. Observe the steady state pressure profile across the column.

Figure 2.159



26. Record the top stage pressure (1\_Main TS). Calculate the theoretical bottom stage pressure as follows:

$$\text{Bottom Stage Pressure} = \text{Top Stage Pressure} + \text{Total Section Pressure Drop} \quad (2.1)$$

Variable	Value
Top Stage Pressure	197.9 kPa
Total Section pressure drop	23.66 kPa
Bottom Stage Pressure	221.56 kPa

27. In the **Pressure** column of the Profiles group, specify a bottom stage pressure (29\_Main TS) of 221.56 kPa.

Figure 2.160

	Stage	Pressure [kPa]	Temp [C]
26_Main TS	27	219.0	348.7
27_Main TS	28	219.9	352.3
28_Main TS	29	220.7	359.7
29_Main TS	30	221.6	315.6
1_Karo SS	21	204.5	220.4





Run Column Solver icon

28. Converge the Column sub-flowsheet by clicking the **Run Column Solver** icon in the tool bar.
29. Close the Column property view.

## Side Stripper Tray Sizing

In this section, you will size the following side stripper operations using the tray sizing utility as described in the Column Tray Sizing section.

- Kero\_SS
  - Diesel\_SS
  - AGO\_SS
1. From the **Tools** menu, select **Utilities**. The Utilities property view appears.
  2. Double-click on the Tray Sizing utility. The Tray Sizing view appears.
  3. In the **Name** field, change the name to Kero\_SS TS.
  4. Click the **Select TS** button. The Select Tray Section view appears.
  5. From the Flowsheet list, select T-100, then select Kero\_SS from the Object list. Click the **OK** button.
  6. Click the **AutoSection** button. The AutoSection view appears.
  7. Click the **Next** button.
  8. Click the **Complete AutoSection** button to calculate the Kero\_SS TS tray sizing parameters.
  9. Record the following tray section parameters available on the **Performance** tab in the **Results** page:

Variable	Kero_SS
Section Diameter	1.676 m
Weir Height	0.0508 m
Tray Spacing	0.6096 m
Weir Length	1.362
Number of Flow Paths	1
Actual Weir Length	1.362

10. Close the Kero\_SS TS tray sizing utility.
11. Repeat steps #2-#8 to size the Diesel\_SS and AGO\_SS side strippers.



12. Click the **Performance** tab, select the **Results** page, then confirm that the following tray section parameters match the table below:

Variable	Diesel_SS	AGO_SS 1	AGO_SS 2
Section Diameter	1.676 m	0.9144 m	0.6096 m
Weir Height	0.0508 m	0.0508 m	0.0508 m
Tray Spacing	0.6096 m	0.6096 m	0.6096 m
Weir Length	3.029 m	0.7767 m	0.5542 m
Number of Flow Paths	2	1	1
Actual Weir Length	1.515 m	0.7767 m	0.5542


The pressure drop rating information found in the side stripper tray sizing utilities is not used to specify the pressure profile of the Side Stripper unit operations. Since there are only three trays in each side stripper, the pressure drop across the respective tray sections is small. Keeping the pressure profile across the side strippers constant does not greatly impact the transition from steady state mode to dynamics.

13. Close the Available Utilities view.

You should still be in the Column sub-flowsheet environment. If not, double-click the Column T-100 and then click the **Column Environment** button on the bottom of the Column property view.

14. In the PFD, double-click the Kero\_SS side stripper icon to open its property view.
15. Click the **Rating** tab, then select the **Sizing** page.
16. Specify the following tray section parameters that were calculated in the previous table:
- Section Diameter
  - Tray Spacing
  - Weir Height
  - Actual Weir Length

**Figure 2.161**





17. Close the Kero\_SS property view.
18. Double-click the Diesel\_SS icon, then specify the tray rating information using the table on the previous page. Close the property view when you are done.
19. Repeat the same procedure to specify the tray rating information for AGO\_SS.
20. After the column has been specified with the tray rating information, converge the column by clicking the **Run Column Solver** icon in the toolbar.
21. Save the case as **DynTUT2-2.hsc**.




Run Column Solver icon

## Vessel Sizing

The Condenser and Kero\_SS\_Reb operations require proper sizing before they can operate effectively in dynamic mode. The volumes of these vessel operations are determined based on a 10 minute liquid residence time.

1. Double-click the Condenser icon on the PFD to open its property view.
2. Click the **Worksheet** tab, then select the **Conditions** page.

Figure 2.162





3. On the **Conditions** page, confirm the following Liquid Volumetric Flow (Std Ideal Liq Vol Flow) of the following streams:

Liquid Volumetric Flow Rate (m3/h)	Value
Reflux	106.7
Naphtha	152.4
Waste Water	5.736
To Condenser	264.8


4. Calculate the vessel volume as follows, assuming a 50% liquid level residence volume and a 10 min. residence time:

$$Vessel\ Volume = \frac{Total\ Liquid\ Exit\ Flow \times Residence\ Time}{0.5} \quad (2.2)$$

The vessel volume calculated for the Condenser is **88.3 m<sup>3</sup>**.

5. Click the **Dynamics** tab, then select the **Specs** page.
6. In the Model Details group, specify the vessel **Volume** as **88.3 m<sup>3</sup>** and the Level Calculator as a Vertical Cylinder.

**Figure 2.163**




7. Close the Condenser property view.
8. In the PFD, double-click the Kero\_SS\_Reb icon to open its property view.



9. Click the **Worksheet** tab, then select the **Conditions** page.

Figure 2.164




10. In the **Conditions** page, confirm that the Liquid Volumetric Flow (Std Ideal Liq Vol Flow) for Kerosene is 61.61 m<sup>3</sup>/h.

Assume a 10 minute of residence time and a 50% liquid level residence volume. The vessel volume calculated for the Kero\_SS\_Reb is 20.5 m<sup>3</sup>.

11. Click the **Dynamics** tab, then select the **Specs** page.
12. In the **Volume** cell, enter 20.5 m<sup>3</sup>. In the **Level Calculator** cell, select Horizontal Cylinder from the drop-down list.

Figure 2.165



13. Close the Kero\_SS\_Reb property view.




## Cooler Volume Sizing

HYSYS assigns a default volume to each Cooler unit operation in the Column sub-flowsheet. In this section you will modify each pump around cooler to initialize with a default vessel volume.

1. Double-click the **PA\_1\_Cooler** operation in the PFD to open the property view.
2. Click the **Dynamics** tab, then select the **Specs** page.
3. In the Model Details group, click in the **Volume** cell, then press **DELETE**. The default volume of 0.10 m<sup>3</sup> appears.
4. In the Dynamic Specifications group, ensure that all the specification checkboxes are inactive. No dynamic specifications should be set for the pump around coolers.

Figure 2.166



5. Close the PA\_1\_Cooler view.
6. Repeat this process for the PA\_2\_Cooler and the PA\_3\_Cooler operations.
7. Save the case as **DynTUT2-3.hsc**.

## 2.3.3 Adding Controller Operations

Controller operations can be added before or after the transition to dynamic mode. Key control loops are identified and controlled using PID Controller logical operations. Although these controllers are not required to run the design in dynamic mode, they increase the realism of the model and provide more stability.



## Adding a Level Controller

In this section you will add level controllers to the simulation flowsheet to control the levels of the condenser and reboiler.

First you will install the Condenser controller.




PID Controller icon

For more information regarding PID Controller, see [Section 12.4.4 - PID Controller](#) of the [Operations Guide](#).

1. If the Object Palette is not visible, press F4.
2. In the Object Palette, click the **PID Controller** icon.
3. In the PFD, click near the Condenser operation. The controller icon, named IC-100, appears in the PFD.
4. Double-click the IC-100 icon to open the controller property view.
5. On the **Connections** tab, click in the **Name** field and change the name of the Controller to Cond LC.
6. In the Process Variable Source group, click the **Select PV** button, then select the information as shown in the figure below. Click the **OK** button when you are done.


Figure 2.167





7. In the Output Target Object group, click the **Select OP** button, then select the information as shown in the figure below. Click the **OK** button when you are finished.

Figure 2.168




8. Click the **Parameters** tab, then select the **Configuration** page.
9. Supply the following for the **Configuration** page:

In this cell...	Enter...
Action	Direct
Kc	4
Ti	5 minutes
PV Minimum	0%
PV Maximum	100%

10. Click the **Control Valve** button. The FCV for Reflux view appears.
11. In the **Max Flow** cell of the Valve Sizing group, enter 2000 kgmole/h.

Figure 2.169




12. Close the FCV for Reflux view.



For more information regarding Face Plates, see [Section 12.13 - Controller Face Plate](#) in the **Operations Guide**.




13. Click the **Face Plate** button. The face plate for Cond LC appears.



14. Change the controller mode to Auto on the face plate by opening the drop-down list and selecting Auto.

15. Double-click the PV cell, then input the set point at 50%.



16. Close the Cond LC property view, but leave the face plate view open.

17. Repeat the procedures you just learned to add a PID Controller operation which serves as the Kero\_SS\_Reb level controller. Specify the following:

Tab [Page]	In this cell...	Enter...
Connections	Name	Reb LC
	Process Variable Source	Kero_SS_Reb, Liq Percent Level
	Output Target Object	Kero_SS_Draw
Parameters [Configuration]	Action	Reverse
	Kc	1
	Ti	5 minutes
	PV Minimum	0%
	PV Maximum	100%

If you cannot locate a stream or operation in the Select Input for PV view, select the **All** radio button in the Object Filter group and look again.

18. Click the **Control Valve** button. The FCV for Kero\_SS\_Draw view appears.



19. In the Valve Sizing group, enter the following

In this cell...	Enter...
<b>Flow Type</b>	MolarFlow
<b>Minimum Flow</b>	0 kgmole/h
<b>Maximum Flow</b>	1000 kgmole/h

20. Close the FCV for Kero\_SS\_Draw view.

21. Click the **Face Plate** button. Change the controller mode to Auto on the face plate, then input a set point of 50%. Leave the face plate view open.

22. Close the Reb LC property view.

## Adding a Flow Controller

In this section you will add flow controllers to the product streams of the column. These controllers ensure that sufficient material is leaving the column.

1. Click the PID Controller icon in the Object Palette, then click in the PFD near the Off Gas stream. The controller icon appears.
2. Double-click the controller icon to access the property view. Specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	Off Gas FC
	Process Variable Source	Off Gas, Molar Flow
	Output Target Object	Atmos Cond
<b>Parameters [Configuration]</b>	Action	Direct
	Kc	0.01
	Ti	5 minutes
	PV Minimum	0 kgmole/h
	PV Maximum	100 kgmole/h

3. Click the **Control Valve** button. The FCV for Atmos Cond view appears.

4. In the Duty Source group, ensure that the **Direct Q** radio button is selected.



5. In the Direct Q group, enter the following details:

In this cell...	Enter...
Minimum Available	0 kJ/h
Maximum Available	$2 \times 10^8$ kJ/h

6. Close the FCV for Atmos Cond view.
7. Click the **Face Plate** button. The Off Gas FC face plate view appears. Change the controller mode to Auto, then input a set point of 5 kgmole/h.
8. Close the Off Gas FC property view, but leave the face plate view open.
9. In the Object Palette, click the **PID Controller** icon, then click in the PFD near the Diesel stream. The controller icon appears in the PFD.
10. Double-click the controller icon to access the property view. then specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	Diesel FC
	Process Variable Source	Diesel, Liq Vol Flow@Std Cond
	Output Target Object	Diesel_SS_Draw
<b>Parameters [Configuration]</b>	Action	Reverse
	Kc	1
	Ti	5 minutes
	PV Minimum	0 m3/h
	PV Maximum	250 m3/h

11. Click the **Control Valve** button. The FCV for Diesel\_SS\_Draw view appears.
12. In the Valve Sizing group, enter the following details:

In this cell...	Enter...
Flow Type	MolarFlow
Minimum Flow	0 kgmole/h
Maximum Flow	1200 kgmole/h

13. Close the FCV for Diesel\_SS\_Draw view.
14. Click the **Face Plate** button. The Diesel FC face plate view appears. Change the controller mode to Auto and input a set point of 127.5 m3/h.



15. Close the property view, but leave the face plate view open.
16. Click the **PID Controller** icon in the Object Palette, then click near the AGO stream on the PFD. The controller icon appears.
17. Double-click the controller icon, then specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	AGO FC
	Process Variable Source	AGO, Liq Vol Flow@Std Cond
	Output Target Object	AGO_SS_Draw
<b>Parameters [Configuration]</b>	Action	Reverse
	Kc	0.7
	Ti	3 minutes
	PV Minimum	0 m3/h
	PV Maximum	60 m3/h

18. Click the **Control Valve** button. The FCV for AGO\_SS\_Draw view appears.
19. In the Valve Sizing group, enter the following details:

In this cell...	Enter...
<b>Flow Type</b>	MolarFlow
<b>Minimum Flow</b>	0 kgmole/h
<b>Maximum Flow</b>	250 kgmole/h

20. Close the FCV for AGO\_SS\_Draw view.
21. Click the **Face Plate** button. The AGO FC face plate view appears. Change the controller mode to Auto and input a set point of 29.8 m3/h.
22. Close the property view, but leave the face plate view open.
23. Save the case as **DynTUT2-4.hsc**.

## 2.3.4 Adding Pressure-Flow Specifications

Before integration can begin in HYSYS, the degrees of freedom for the flowsheet must be reduced to zero by setting the pressure-flow specifications. Normally, you make one pressure-flow specification per flowsheet boundary stream, however, there are exceptions to the rule. One extra pressure flow specification is required for every condenser or side stripper unit operation attached to the main column. This rule



applies only if there are no pieces of equipment attached to the reflux stream of the condenser or the draw stream of the side strippers. Without other pieces of equipment (i.e., pumps, coolers, valves) to define the pressure flow relation of these streams, they must be specified with a flow specification.

Pressure-flow specifications for this case will be added to the following boundary streams:

- Atm Feed
- Main Steam
- AGO Steam
- Diesel Steam
- Off Gas
- Waste Water
- Naphtha
- Kerosene
- Diesel
- AGO
- Residue

For more information regarding Pressure Flow specifications in Column unit operations see [Chapter 8 - Column](#) in Operations Guide.

This simplified column has all the feed streams specified with a flow specification. The Off Gas stream has a pressure specification which defines the pressure of the condenser and consequently the entire column. The liquid exit streams of the column and the side stripper operations require pressure specifications since there are no attached pieces of equipment in these streams. All the other exit streams associated with the column require flow specifications.

The following pump around streams require flow specifications since both the Pressure Flow and the Delta P specifications are not set for the pump around coolers.

- PA\_1\_Draw
- PA\_2\_Draw
- PA\_3\_Draw

The following streams have their flow specifications defined by PID Controller operations.

- Reflux
- Kero\_SS\_Draw
- Diesel\_SS\_Draw
- AGO\_SS\_Draw





Enter Parent Simulation  
Environment icon




Dynamic Mode icon

1. Enter the Main Flowsheet environment. Close the column property view if it is still open.
2. Switch to dynamic mode by clicking the **Dynamic Mode** icon. When asked if you want to allow dynamics assistant to identify items which are needed to be addressed before proceeding into dynamics, click the **No** button.

Every material stream in the Main Flowsheet requires either a pressure or flow specification.

3. Double-click the Diesel Steam icon to enter its property view.
4. Click the **Dynamics** tab, then select the **Specs** page.
5. In the Pressure Specification group, clear the **Active** checkbox.
6. In the Flow Specification group, select the **Molar** radio button, then activate the **Active** checkbox.
7. In the **Molar Flow** cell, enter 75.54 kgmole/h if required.

Figure 2.172



Once a pressure or flow specification has been made active, the stream value turns blue and can be modified.



8. Set the following pressure or flow specifications for the following streams in the Main Flowsheet.

Material Stream	Pressure Specification	Flow Specification	Value
<b>Atm Feed</b>	Inactive	Molar Flow, Active	2826 kgmole/h
<b>Main Steam</b>	Inactive	Molar Flow, Active	188.8 kgmole/h
<b>AGO Steam</b>	Inactive	Molar Flow, Active	62.95 kgmole/h
<b>Off Gas</b>	Active	Inactive	135.8 kPa
<b>Waste Water</b>	Inactive	Molar Flow, Active	317.8 kgmole/h
<b>Naphtha</b>	Inactive	Ideal LiqVol, Active	152.4 m3/h
<b>Kerosene</b>	Inactive	Ideal LiqVol, Active	61.61 m3/h
<b>Diesel</b>	Active	Inactive	211.4 kPa
<b>AGO</b>	Active	Inactive	215.6 kPa
<b>Residue</b>	Active	Inactive	221.6 kPa

9. Use the Object Navigator to enter the Column subflowsheet environment. Click the **Object Navigator** icon in the tool bar. The Object Navigator view appears. In the Flowsheets group, double-click T-100.


Every material stream in the column environment also requires either a pressure or flow specification. Use the following procedure to set a pressure-flow specification for the PA\_1\_Draw stream.

10. In the PFD, double-click the PA\_1\_Draw stream icon to open the property view.
11. Click the **Dynamics** tab, then select the **Specs** page.



12. In the Flow Specification group, select the **Molar** radio button, then activate the **Active** checkbox.

Figure 2.173



13. Close the PA\_1\_Draw property view.
14. Activate the following flow specifications for the following streams in the Column sub-flowsheet.

Material Stream	Pressure-Flow Specification	Value
PA_2_Draw	Molar Flow	830.2 kgmole/h
PA_3_Draw	Molar Flow	648.0 kgmole/h
Reflux	Molar Flow	879.7 kgmole/h
Kero_SS_Draw	Molar Flow	426.6 kgmole/h
Diesel_SS_Draw	Molar Flow	616.8 kgmole/h
AGO_SS_Draw	Molar Flow	124.8 kgmole/h

15. Save the case as **DynTUT2-5.hsc**.
16. Close all the views except the face plates.
17. To arrange the face plates, select the **Arrange Desktop** command from the **Windows** menu.
18. The integrator can be run at this point. Click the **Start Integrator** icon. When you are given the option to run dynamic assistant, select **No**.




Start Integrator icon



When the integrator initially runs, HYSYS detects that no vapour phase exists in the Condenser at the specified process conditions. It displays the following message:

Figure 2.174



HYSYS recommends that you increase the temperature setting to create a vapour phase. You can also create a non-equilibrium vapour phase or set the liquid level to be 100%. For the sake of this example, select the default recommendation.

19. Click the **Increase Temperature** button.
20. Let the integrator run for few minutes so all the values can propagate through the column. Observe the value changes on the face plate view.
21. To stop the integrator, click the **Stop Integrator** icon.




## 2.3.5 Monitoring in Dynamics

Now that the model is ready to run in dynamic mode, the next step is to install a strip chart to monitor the general trends of key variables. The following is a general procedure for installing strip charts in HYSYS.

1. Open the Databook by using the hot key combination CTRL D.


Figure 2.175



The Variable Navigator is used extensively in HYSYS for locating and selecting variables. The Navigator operates in a left-to-right manner-the selected Flowsheet determines the Object list, the chosen Object dictates the Variable list, and the selected variable determines whether any Variable Specifics are available.

2. On the **Variables** tab, click the **Insert** button. The Variable Navigator view appears.
3. In the Flowsheet list, select the Column T-100.
4. In the Object Filter group, select the **UnitOps** radio button. The Object list is filtered to show unit operations only.
5. In the Object list, select the Condenser. The Variable list available for the column appears to the right of the Object list.
6. In the Variable list, select Liquid Percent Level.

Figure 2.176





If you can't find an Object in the Variable Navigator view, select the **All** radio button in the Object Filter group, then select Case (Main) in the Flowsheet group. All operations and streams for the design will appear in the Object list.


7. Click the **OK** button. The variable now appears in the Databook.
8. Add the following variables to the Databook. If you select the top variable in the list of Available Data Entries before inserting a new variable, the new variable will always be added to the top of the list.

Object	Variable
Kero_SS_Reb	Liquid Percent Level
Off Gas	Molar Flow
Condenser	Vessel Temperature

The next task is to create a Strip Chart to monitor the dynamics behaviour of the selected variables.

9. Click the **Strip Charts** tab in the Databook view.
10. Click the **Add** button. HYSYS creates a new Strip Chart with the default name DataLogger1.
11. Click in the blank **Active** checkbox beside the Condenser/Liquid Percent Level variable.
12. Repeat step #11 to activate the other variables as shown below.

Figure 2.177



For more information about the Strip Chart setup, refer to [Section 11.7.3 - Strip Charts](#) in the **User Guide**.

13. Select DataLogger1 in the list of Available Strip Charts group, then click the **Setup** button to open the Logger Setup view. This view allows you to customize how the data appears on the Strip Chart. Close the Logger Setup view.
14. Click the **Strip Chart** button in the View group to display the DataLogger1 strip chart.

You are now ready to begin dynamics calculations. The DataLogger1 view should be visible.





Start Integrator Icon

To view a legend for the variables, right-click anywhere in the DataLogger window and select **Legend** from the menu that appears.

15. Start the Integrator by clicking the **Start Integrator** Icon. If you get a warning notice regarding the dynamics assistant, click the **No** button.
16. Observe as the variables line out in the DataLogger1 view. Move the cursor over the lines in the graph to view the variable label. Maximize the DataLogger1 view if required.
17. Click the **Stop Integrator** icon when you want to stop the simulation.
18. Perform an analysis by manipulating design variables and using the Databook tools to observe the response of other variables.



# 3 Chemicals Tutorial

<b>3.1 Introduction .....</b>	<b>3</b>
<b>3.2 Steady State Simulation .....</b>	<b>4</b>
3.2.1 Process Description .....	4
3.2.2 Setting Your Session Preferences .....	5
3.2.3 Defining the Fluid Package .....	8
3.2.4 Defining the Reaction .....	17
3.2.5 Entering the Simulation Environment .....	26
3.2.6 Using the Workbook .....	28
3.2.7 Installing Equipment on the PFD .....	46
3.2.8 Viewing Results .....	66
<b>3.3 Dynamic Simulation .....</b>	<b>76</b>
3.3.1 Simplifying the Steady State Flowsheet .....	77
3.3.2 Using the Dynamics Assistant .....	78
3.3.3 Modeling a CSTR Open to the Atmosphere .....	82
3.3.4 Adding Controller Operations .....	86
3.3.5 Monitoring in Dynamics .....	92








## 3.1 Introduction

The complete case for this tutorial has been pre-built and is located in the file **TUTOR3.HSC** in your **HYSYS\Samples** directory.

In this tutorial, a flowsheet for the production of propylene glycol is presented. Propylene oxide is combined with water to produce propylene glycol in a continuously-stirred-tank reactor (CSTR). The reactor outlet stream is then fed to a distillation tower, where essentially all the glycol is recovered in the tower bottoms. A flowsheet for this process appears below.

Figure 3.1



The following pages will guide you through building a HYSYS case for modeling this process. This example will illustrate the complete construction of the simulation, including selecting a property package and components, defining the reaction, installing streams and unit operations, and examining the final results. The tools available in HYSYS interface will be utilized to illustrate the flexibility available to you.

Before proceeding, you should have read [Chapter A - HYSYS Tutorials](#) which precedes the tutorials in this manual.



## 3.2 Steady State Simulation


### 3.2.1 Process Description

The simulation will be built using these basic steps:

1. Create a unit set.
2. Choose a property package.
3. Select the components.
4. Define the reaction.
5. Create and specify the feed streams.
6. Install and define the Mixer and Reactor.
7. Install and define the Distillation Column.

The process being modeled in this example is the conversion of propylene oxide and water to propylene glycol in a CSTR Reactor. The reaction products are then separated in a distillation tower. A flowsheet for this process appears below.

**Figure 3.2**



The propylene oxide and water feed streams are combined in a Mixer. The combined stream is fed to a Reactor, operating at atmospheric pressure, in which propylene glycol is produced. The Reactor product stream is fed to a distillation tower, where essentially all the glycol is recovered in the bottoms product.

The Workbook displays information about streams and unit operations in a tabular format, while the PFD is a graphical representation of the flowsheet.

The two primary building tools, Workbook and PFD, are used to install the streams and operations, and to examine the results while progressing through the simulation. Both of these tools provide you with a large amount of flexibility in building your simulation and in quickly accessing the information you need.

The Workbook is used to build the first part of the flowsheet, including the feed streams and the mixer. The PFD is then used to install the reactor, and a special sequence of views called the Input Expert will be used to install the distillation column.




## 3.2.2 Setting Your Session Preferences

Start HYSYS and create a new case. Your first task is to set your Session Preferences.

1. From the **Tools** menu, select **Preferences**. The Session Preferences view appears.

Figure 3.3



2. The **Simulation** tab, **Options** page should be visible. Ensure that the **Use Modal Property Views** checkbox is unchecked.
3. Click the **Variables** tab, then select the **Units** page.



## Creating a New Unit Set


The first task you perform when building the simulation case is choosing a unit set. HYSYS does not allow you to change any of the three default unit sets listed, however, you can create a new unit set by cloning an existing one. For this tutorial, you will create a new unit set based on the HYSYS Field set, then customize it


1. In the Available Units Sets list, select Field.

The default unit for Liq. Vol. Flow is barrel/day; next you will change the Liq. Vol. Flow units to USGPM.

The default Preference file is named **HYSYS.prf**. When you modify any of the preferences, you can save the changes in a new Preference file by clicking the **Save Preference Set** button. HYSYS prompts you to provide a name for the new Preference file, which you can later recall into any simulation case by clicking the **Load Preference Set** button.


Figure 3.4



2. Click the **Clone** button. A new unit set named NewUser appears in the Available Unit Sets list.
3. In the **Unit Set Name** field, change the name to Field-USGPM. You can now change the units for any variable associated with this new unit set.
4. Find the **Liq. Vol. Flow** cell. Click in the **barrel/day** cell beside it.
5. To open the list of available units, click the down arrow , or press the F2 key then the Down arrow key.



- From the list, select USGPM.

**Figure 3.5**

- Your new unit set is now defined. Close the Session Preferences view.



## 3.2.3 Defining the Fluid Package



New Case Icon

All commands accessed via the tool bar are also available as menu items.


HYSYS displays the current **Environment** and **Mode** in the upper right corner of the view. Whenever you begin a new case, you are automatically placed in the **Basis** Environment, where you can define your property package and components.

The Simulation Basis Manager allows you to create, modify, and otherwise manipulate Fluid Packages in your simulation case. Most of the time, as with this example, you will require only one Fluid Package for your entire simulation.

HYSYS has created a Fluid Package with the default name **Basis-1**. You can change the name of this fluid package by typing a new name in the **Name** cell at the bottom of the view.

1. Click the **New Case** icon.
2. The Simulation Basis Manager appears.

Figure 3.6




The next task is to create a Fluid Package. A Fluid Package, at minimum, contains the components and property method that HYSYS will use in its calculations for a particular flowsheet. Depending on what a specific flowsheet requires, a Fluid Package may also contain other information such as reactions and interaction parameters.

## Creating a Fluid Package

1. Click the **Fluid Pkgs** tab of the Simulation Basis Manager.
2. Click the **Add** button. The Fluid Package property view appears.

Figure 3.7






The Fluid Package property view allows you to supply all the information required to completely define the Fluid Package. In this tutorial you will use the following tabs: Set Up, Binary Coeffs (Binary Coefficients), and Rxns (Reactions).

You choose the Property Package on the Set Up tab. The currently selected property package is <none>. There are a number of ways to select the desired base property package, in this case UNIQUAC.

3. Do **one** of the following:


- Begin typing UNIQUAC, and HYSYS finds the match to your input.
- Use the vertical scroll bar to move down the list until UNIQUAC becomes visible, then click on it.

**Figure 3.8**




The Property Pkg indicator bar at the bottom of the view now indicates UNIQUAC is the current property package for this Fluid Package.

**Figure 3.9**



Alternatively, you can select the Activity Models radio button in the Property Pkg Filter group, producing a list of only those property packages which are Activity Models. UNIQUAC appears in the filtered list, as shown here.

**Figure 3.10**






In the Component List Selection drop-down list, HYSYS filters to the library components to include only those appropriate for the selected Property Package. In this case, no components have yet been defined.

## Selecting Components

Now that you have chosen the property package to be used in the simulation, your next task is to select the components.

1. In the Component List Selection group, click the **View** button. The Component List View appears.

Figure 3.11



Each component can appear in three forms, corresponding to the three radio buttons that appear above the component list.

Feature	Description
<b>SimName</b>	The name appearing within the simulation.
<b>FullName/Synonym</b>	IUPAC name (or similar), and synonyms for many components.
<b>Formula</b>	The chemical formula of the component. This is useful when you are unsure of the library name of a component, but know its formula.




Based on the selected radio button, HYSYS locates the component(s) that best matches the information you type in the Match field.

In this tutorial you will use propylene oxide, propylene glycol and H<sub>2</sub>O. First, you will add propylene oxide to the component list.

2. Ensure the **SimName** radio button is selected and the **Show Synonyms** checkbox is checked.
3. In the **Match** field, start typing propyleneoxide, as one word. HYSYS filters the list as you type, displaying only those components that match your input.

**Figure 3.12**





4. When propylene oxide is selected in the list, add it to the Selected Components List by doing one of the following:
  - Press the **ENTER** key.
  - Click the **Add Pure** button.
  - Double-click on **PropyleneOxide**.



The component now appears in the Selected Components List.

Figure 3.13



Another method for finding components is to use the View Filters to display only those components belonging to certain families.


Next, you will add Propylene Glycol to the component list using the filter.

5. Ensure the **Match** field is empty by pressing ALT M and then the DELETE key.
6. Click the **View Filters** button. The Filters view appears.
7. Click the **Use Filter** checkbox to activate the filter checkboxes.
8. Since Propylene Glycol is an alcohol, click the **Alcohols** checkbox.



9. In the **Match** field, begin typing propyleneglycol, as one word. HYSYS filters as you type, displaying only the alcohols that match your input.

Figure 3.14



10. When Propylene Glycol is selected in the list, press the ENTER key to add it to the Selected Components list.

Finally, you will add the component H2O.


11. In the Filter view, clear the **Alcohols** checkbox by clicking on it.
12. Ensure the **Match** field is empty by pressing ALT M and then the DELETE key
13. H2O does not fit into any of the standard families, so click on the **Miscellaneous** checkbox.
14. Scroll down the filtered list until H2O is visible, then double-click on H2O to add it to the Selected Components list.



15. The final component list appears below.

A component can be removed from the Selected Components list by selecting it and clicking the **Remove** button or the **DELETE** key.

**Figure 3.15**




## Viewing Component Properties

To view the properties of one or more components, select the component(s) and click the View Component button. HYSYS opens the property view(s) for the component(s) you select.

1. Click on 12C3diol in the Selected Components List.
2. Click the **View Component** button. The property view for the component appears.

**Figure 3.16**





The Component property view provides you with complete access to the pure component information for viewing only. You cannot modify any parameters for a library component, however, HYSYS allows you to clone a library component into a Hypothetical component, which can then be modified as desired. Refer to [Chapter 3 - Hypotheticals](#) in the Simulation Basis manual for more information on cloning library components.


3. Close the individual component view, then close the Component List View to return to the Fluid Package.

## Providing Binary Coefficients

The next task in defining the Fluid Package is providing the binary interaction parameters.

1. Click the **Binary Coeffs** tab of the Fluid Package view..

Figure 3.17



In the Activity Model Interaction Parameters group, the Aij interaction table appears by default. HYSYS automatically inserts the coefficients for any component pairs for which library data is available. You can change any of the values provided by HYSYS if you have data of your own.




In this case, the only unknown coefficients in the table are for the 12C3Oxide/12-C3diol pair. You can enter these values if you have available data, however, for this example, you will use one of HYSYS' built-in estimation methods instead.

Next, you will use the UNIFAC VLE estimation method to estimate the unknown pair.

2. In the Coeff Estimation group, ensure the **UNIFAC VLE** radio button is selected.
3. Click the **Unknowns Only** button. HYSYS provides values for the unknown pair. The final Activity Model Interaction Parameters table for the Aij coefficients appears below.

**Figure 3.18**



	12C3Oxide	12-C3diol	H2O
12C3Oxide	---	-170.570	-71.909
12-C3diol	787.060	---	-335.033
H2O	823.550	-5.027	---

4. To view the Bij coefficient table, select the **Bij** radio button. For this example, all the Bij coefficients will be left at the default value of zero.




## 3.2.4 Defining the Reaction



Basis Icon

1. Return to the Simulation Basis Manager view by clicking on its title bar, or by clicking the **Basis** icon.
2. Click the **Reactions** tab. This tab allows you to define all the reactions for the flowsheet.

Figure 3.19



The reaction between water and propylene oxide to produce propylene glycol is as follows:

These steps will be followed in defining our reaction:

1. Create and define a Kinetic Reaction.
2. Create a Reaction Set containing the reaction.
3. Activate the Reaction set to make it available for use in the flowsheet.



## Selecting the Reaction Components

The first task in defining the reaction is choosing the components that will be participating in the reaction. In this tutorial, all the components that were selected in the Fluid Package are participating in the reaction, so you do not have to modify this list. For a more complicated system, however, you would add or remove components from the list.

To add or remove a component, click the Add Comps button. The Component List View appears. Refer to the [Selecting Components](#) section in [Section 3.2.3 - Defining the Fluid Package](#) for more information.




## Creating the Reaction

Once the reaction components have been chosen, the next task is to create the reaction.

1. In the Reactions group, click the **Add Rxn** button. The Reactions view appears.

Figure 3.20




2. In the list, select the Kinetic reaction type, then click the **Add Reaction** button. The Kinetic Reaction property view appears, opened to the **Stoichiometry** tab.

On the Stoichiometry tab, you can specify which of the Rxn Components are involved in the particular reaction as well as the stoichiometry and the reaction order.

Often you will have more than one reaction occurring in your simulation case. On the Stoichiometry tab of each reaction, select only the Rxn Components participating in that reaction.

Figure 3.21



3. In the Component column, click in the cell labeled **\*\*Add Comp\*\***.
4. Select **Water** as a reaction component by doing **one** of the following:
  - Open the drop-down list and select H2O from the list of available reaction components.
  - Type H2O. HYSYS filters as you type, searching for the component which matches your input. When H2O is selected, press the **ENTER** key to add it to the Component list.
5. Repeat this procedure to add 12C3Oxide and 12-C3diol to the reaction table.



The next task is to enter the stoichiometric information. A negative stoichiometric coefficient indicates that the component is consumed in the reaction, while a positive coefficient indicates the component is produced.

6. In the Stoich Coeff column, click in the <<empty>> cell corresponding to H<sub>2</sub>O.
7. Type -1 and press the ENTER key.
8. Enter the coefficients for the remaining components as shown in the view below:

Figure 3.22

Component	Mole Wt	Stoich Coeff	Fwd Order	Rev Order
H <sub>2</sub> O	18.015	-1.000	1.00	0.00
12C3Oxide	58.080	-1.000	1.00	0.00
12-C3diol	76.096	1.000	0.00	1.00
*Add Comp™				

Balance Error: 0.00000  
Reaction Heat (25 C): -3.9e+04 Btu/lbmole

Stoichiometry Basis Parameters  
Delete Name: Rxn-1 Not Ready

Once the stoichiometric coefficients are supplied, the Balance Error cell will show 0 (zero), indicating that the reaction is mass balanced. HYSYS will also calculate and display the heat of reaction in the Reaction Heat cell. In this case, the Reaction Heat is negative, indicating that the reaction produces heat (exothermic).

HYSYS provides default values for the Forward Order and Reverse Order based on the reaction stoichiometry. The kinetic data for this Tutorial is based on an excess of water, so the kinetics are first order in Propylene Oxide only.



9. In the **Fwd Order** cell for H<sub>2</sub>O, change the value to 0 to reflect the excess of water. The **Stoichiometry** tab is now completely defined and appears as shown below.

Notice that the default values for the Forward Order and Reverse Order appear in red, indicating that they are suggested by HYSYS. When you enter the new value for H<sub>2</sub>O, it will be blue, indicating that you have specified it.

Figure 3.23

**Kinetic Reaction: Rxn-1**

Stoichiometry and Rate Info

Component	Mole Wt.	Stoich Coeff	Fwd Order	Rev Order
H <sub>2</sub> O	18.015	-1.000	0.00	0.00
12C3Oxide	58.080	-1.000	1.00	0.00
12-C3diol	76.096	1.000	0.00	1.00
*Add Comp**				

Balance Error: 0.00000  
Reaction Heat (25 C): -3.9e+04 Btu/lbmole

**Stoichiometry** Basis Parameters

Delete Name: Rxn-1 Not Ready

The next task is to define the reaction basis.

10. In the Kinetic Reaction view, click the **Basis** tab.
11. In the **Basis** cell, accept the default value of Molar Conc.
12. Click in the **Base Component** cell. By default, HYSYS has chosen the first component listed on the **Stoichiometry** tab, in this case H<sub>2</sub>O, as the base component.
13. Change the base component to Propylene Oxide by doing **one** of the following:
  - Open the drop-down list of components and select 12C3Oxide.
  - Begin typing 12C3Oxide, and HYSYS filters as you type. When 12C3Oxide is selected, press the **ENTER** key.



You can have the same reaction occurring in different phases with different kinetics and have both calculated in the same **REACTOR**.

- In the **Rxn Phase** cell, select **CombinedLiquid** from the drop-down list. The completed **Basis** tab appears below.

Figure 3.24

**Kinetic Reaction: Rxn-1**

Basis

Basis	Molar Conc'n
Base Component	12C3Oxide
Rxn Phase	CombinedLiquid
Min. Temperature	-459.7 F
Max Temperature	5432 F
Basis Units	lbmole/t3
Rate Units	lbmole/t3-hr

Stoichiometry **Basis** Parameters

Delete Name **Rxn-1** **Not Ready**

The Min. Temperature, Max. Temperature, Basis Units and Rate Units are acceptable at their default values.

- Click the **Parameters** tab. On this tab you provide the Arrhenius parameters for the kinetic reaction. In this case, there is no Reverse Reaction occurring, so you only need to supply the Forward Reaction parameters:
- In the Forward Reaction A cell, enter 1.7e13.
- In the Forward Reaction E cell (activation energy), enter 3.24e4 (Btu/lbmole).

The status indicator at the bottom of the Kinetic Reaction property view changes from Not Ready to Ready, indicating that the reaction is completely defined. The final Parameters tab appears below.

Figure 3.25

**Kinetic Reaction: Rxn-1**

Forward Reaction

A	1.7000e+013
E	32400
B	<empty>

Reverse Reaction

A'	<empty>
E'	<empty>
B'	<empty>

Equation Help

$r = k \cdot f(\text{Basis}) - k' \cdot f(\text{Basis})$   
 $k = A \cdot \exp \{ -E / RT \} \cdot T^b$   
 $k' = A' \cdot \exp \{ -E' / RT \} \cdot T^{b'}$   
 T in Kelvin

Stoichiometry Basis **Parameters**

Delete Name **Rxn-1** **Ready**






Basis Icon

18. Close both the Kinetic Reaction property view and the Reactions view.
19. Click the **Basis** icon to ensure the Simulation Basis Manager view is active. On the **Reactions** tab, the new reaction, Rxn-1, now appears in the Reactions group.

Figure 3.26



The next task is to create a reaction set that will contain the new reaction. In the Reaction Sets list, HYSYS provides the Global Rxn Set (Global Reaction Set) which contains all of the reactions you have defined. In this tutorial, since there is only one REACTOR, the default Global Rxn Set could be attached to it, however, for illustration purposes, a new reaction set will be created.

## Creating a Reaction Set


The same reaction(s) can be in multiple Reaction Sets.

Reaction Sets provide a convenient way of grouping related reactions. For example, consider a flowsheet in which a total of five reactions are taking place. In one REACTOR operation, only three of the reactions are occurring (one main reaction and two side reactions). You can group the three reactions into a Reaction Set, then attach the set to the appropriate REACTOR unit operation.




1. In the Reaction Sets group, click the **Add Set** button. The Reaction Set property view appears with the default name Set-1.

Figure 3.27



The drop-down list contains all reactions in the Global Reaction Set. Currently, **Rxn-1** is the only reaction defined, so it is the only available selection.




2. In the Active List, click in the cell labeled **<empty>**.
3. Open the drop-down list and select Rxn-1.

A checkbox labeled OK automatically appears next to the reaction in the Active List. The reaction set status bar changes from Not Ready to Ready, indicating that the new reaction set is complete.

4. Close the Reaction Set view to return to the Simulation Basis Manager. The new reaction set named Set-1 now appears in the Reaction Sets group.

Figure 3.28






## Making the Reaction Set Available to the Fluid Package

The final task is to make the set available to the Fluid Package, which also makes it available in the flowsheet.


1. Click on **Set-1** in the Reaction Sets group on the Reactions tab.
2. Click the **Add to FP** button. The Add 'Set-1' view appears. This view prompts you to select the Fluid Package to which you would like to add the reaction set. In this example, there is only one Fluid Package, Basis-1.

Figure 3.29




3. Select Basis-1, then click the **Add Set to Fluid Package** button.

Figure 3.30





4. Click the **Fluid Pkgs** tab to view a summary of the completed Fluid Package.

**Figure 3.31**

The list of Current Fluid Packages displays the new Fluid Package, Basis-1, showing the number of components (NC) and property package (PP). The new Fluid Package is assigned by default to the Main Simulation, as shown in the Flowsheet-Fluid Pkg Associations group. Now that the Basis is defined, you can install streams and operations in the Simulation environment (also referred to as the Parent Simulation environment or Main Simulation environment).



## 3.2.5 Entering the Simulation Environment




Enter Simulation  
Environment Icon

To leave the Basis environment and enter the Simulation environment, do one of the following:

- Click the **Enter Simulation Environment** button on the Simulation Basis Manager.
- Click the **Enter Simulation Environment** icon on the toolbar.

When you enter the Simulation environment, the initial view that appears is dependent on your current preference setting for the Initial Build Home View. Three initial views are available, namely the PFD, Workbook and Summary. Any or all of these can be displayed at any time, however, when you first enter the Simulation environment, only one is displayed. For this example, the initial Home View is the Workbook (HYSYS default setting).

Figure 3.32





There are several things to note about the Main Simulation environment. In the upper right corner, the Environment has changed from Basis to Case (Main). A number of new items are now available on the Menu and Toolbar, and the Workbook and Object Palette are open on the Desktop. These two latter objects are described below.

You can toggle the palette open or closed by pressing **F4**, or by choosing **Open/Close Object Palette** from the Flowsheet menu.

Features	Description
<b>Workbook</b>	A multiple-tab view containing information about the objects (streams and unit operations) in the simulation case. By default, the Workbook has four tabs, namely Material Streams, Compositions, Energy Streams and Unit Ops. You can edit the Workbook by adding or deleting tabs and changing the information displayed on any tab.
<b>Object Palette</b>	A floating palette of buttons that can be used to add streams and unit operations.

Before proceeding any further to install streams or unit operations, save your case.



Save Icon

1. Do **one** of the following:
  - Click the **Save** icon on the toolbar.
  - From the **File** menu, select **Save**.
  - Press **CTRL S**.

If this is the first time you have saved your case, the Save Simulation Case As view appears. By default, the File Path is the Cases sub-directory in your HYSYS directory.



Open Case Icon

When you choose to open an existing case by clicking the **Open Case** button, or by selecting **Open Case** from the **File** menu, HYSYS allows you to retrieve backup (\*.bk\*) and HYSIM (\*.sim) files in addition to standard HYSYS (\*.hsc) files.

2. In the **File Name** cell type a name for the case, for example GLYCOL. You do not have to enter the **.hsc** extension; HYSYS automatically adds it for you.
3. Once you have entered a file name, press the ENTER key or the **OK** button. HYSYS will now save the case under the name you have given it when you Save in the future. The Save As view will not appear again unless you choose to give it a new name using the Save As command.

If you enter a name that already exists in the current directory, HYSYS will ask you for confirmation before over-writing the existing file.



## 3.2.6 Using the Workbook

### Installing the Feed Streams

In general, the first task you perform when you enter the Simulation environment is to install one or more feed streams. In this section, you will install feed streams using the Workbook.




Workbook Icon

HYSYS accepts blank spaces within a stream or operation name.

1. Click the **Workbook** icon on the toolbar to make the Workbook active.
2. On the **Material Streams** tab, click in the **\*\*New\*\*** cell in the Name row.
3. Type the new stream name Prop Oxide, then press ENTER. HYSYS automatically creates the new stream.

Figure 3.33



When you pressed ENTER after typing in the stream name, HYSYS automatically advanced the active cell down one cell, to Vapour Fraction.


Next you will define the feed conditions for temperature and pressure, in this case 75°F and 1.1 atm.

4. Click in the **Temperature** cell for Prop Oxide.



5. Type 75 in the **Temperature** cell. In the Unit drop-down list, HYSYS displays the default units for temperature, in this case F.

Figure 3.34




6. Since this is the correct unit, press ENTER. HYSYS accepts the temperature.
7. Click in the **Pressure** cell for Prop Oxide.

If you know the stream pressure in another unit besides the default of psia, HYSYS will accept your input in any one of a number of different units and automatically convert to the default for you. For example, you know the pressure of Prop Oxide is 1.1 atm.

8. Type 1.1.
9. Press the SPACEBAR or click on . Begin typing 'atm'. HYSYS will match your input to locate the unit of your choice.

Figure 3.35





- Alternatively, you can specify the unit simply by selecting it from the unit drop-down list.

- ## Providing Compositional Input

12. In the Workbook, double-click the **Molar Flow** cell of the Prop Oxide stream.

The Input Composition for Stream view appears. This view allows you to complete the compositional input.

[illegible]

3-30



The following table lists and explains the features available to you on the Input Composition for Stream view.

Features	Description
<b>Compositional Basis Radio Buttons</b>	You can input the stream composition in some fractional basis other than Mole Fraction, or by component flows, by selecting the appropriate radio button before providing your input.
<b>Normalizing</b>	<p>The Normalizing feature is useful when you know the relative ratios of components; for example, 2 parts N<sub>2</sub>, 2 parts CO<sub>2</sub>, 120 parts C<sub>1</sub>, etc. Rather than manually converting these ratios to fractions summing to one, simply enter the individual numbers of parts and click the <b>Normalize</b> button. HYSYS computes the individual fractions to total 1.0.</p> <p>Normalizing is also useful when you have a stream consisting of only a few components. Instead of specifying zero fractions (or flows) for the other components, simply enter the fractions (or the actual flows) for the non-zero components, leaving the others &lt;empty&gt;. Click the <b>Normalize</b> button, and HYSYS forces the other component fractions to zero.</p>
<b>Calculation status/colour</b>	<p>As you input the composition, the component fractions (or flows) initially appear in red, indicating the final composition is unknown. These values become blue when the stream composition is calculated. Three scenarios result in the stream composition being calculated:</p> <ul style="list-style-type: none"> <li>• Input the fractions of all components, including any zero components, such that their total is exactly 1.0000. Click the <b>OK</b> button.</li> <li>• Input the fractions (totalling 1.000), flows or relative number of parts of all non-zero components. Click the <b>Normalize</b> button, then click the <b>OK</b> button.</li> <li>• Input the flows or relative number of parts of all components, including any zero components, then click the <b>OK</b> button.</li> </ul>

These are the default colours; yours may appear differently depending on your settings on the Colours page of the Session Preferences.

13. In the Composition Basis group, ensure that the **Mole Fractions** radio button is selected.
14. Click on the input cell for the first component, 12C3Oxide. This stream is 100% propylene oxide.
15. Type 1 for the mole fraction, then press ENTER.

In this case, 12C3Oxide is the only component in the stream.









## Adding Another Stream

Next, you will use an alternative method for adding a stream.

18. To add the second feed stream, do any **one** of the following:

- Press **F11**.
- From the **Flowsheet** menu, select **Add Stream**.
- Double-click the **Material Stream** icon on the Object Palette.
- Click the **Material Stream** icon on the Object Palette, then click the Palette's **Add Object** button.

A new stream appears in the Workbook and is named according to the Auto Naming setting in your Session Preferences settings. The default setting names new material streams with numbers, starting at 1 (and energy streams starting at Q-100).

When you create the new stream, the stream's property view also appears, displaying the **Conditions** page of the **Worksheet** tab.

19. In the **Stream Name** cell, change the name to Water Feed.

20. In the **Temperature** cell, enter 75°F.

21. In the **Pressure** cell, enter 16.17 psia.

These parameters are in default units, so there is no need to change the units.

**Figure 3.39**

Water Feed

Worksheet	Stream Name	Water Feed
Conditions	Vapour / Phase Fraction	<empty>
	Temperature [F]	75.000
	Pressure [psia]	16.170
	Molar Flow [lbmole/hr]	<empty>
	Mass Flow [lb/hr]	<empty>
	Std Ideal Liq Vol Flow [USGPM]	<empty>
	Molar Enthalpy [Btu/lbmole]	<empty>
	Molar Entropy [Btu/lbmole-F]	<empty>
	Heat Flow [Btu/hr]	<empty>
	Liq Vol Flow @Std Cond [barrel/day]	<empty>
Fluid Package	Basis-1	

Worksheet Attachments Dynamics


Unknown Compositions

Delete Define from Other Stream...



22. Select the **Composition** page to enter the compositional input for the new feed stream.


Figure 3.40



For the current Composition Basis setting, you want to enter the stream composition on a mass flow basis.


23. Click the **Edit** button near the bottom of the Composition page. The Input Composition for Stream view appears.
24. In the Composition Basis group, change the basis to **Mass Flows** by selecting the appropriate radio button, or by pressing ALT A.
25. In the **CompMassFlow** cell for H2O, type 11,000 (lb/hr), then press ENTER.

Figure 3.41





- Figure 3.42**



**Figure 3.43**





The compositions currently appear in Mass Flow, but you can change this by clicking the Basis button and choosing another Composition Basis radio button.

28. Click the **Conditions** page to view the calculated stream properties. You can display the properties of all phases by resizing the property view




Sizing Arrow Icon

29. Place the cursor over the right border of the view. The cursor changes to a double-ended sizing arrow.

30. With the sizing arrow visible, click and drag to the right until the horizontal scroll bar disappears, making the entire table visible.

Figure 3.44



New or updated information is automatically and instantly transferred among all locations in HYSYS.

In this case, the aqueous phase is identical to the overall phase.

31. Close the Water Feed property view to return to the Workbook.



## Installing Unit Operations

Now that the feed streams are known, your next task is to install the necessary unit operations for producing the glycol.

### Installing the Mixer


The first operation is a Mixer, used to combine the two feed streams. As with most commands in HYSYS, installing an operation can be accomplished in a number of ways. One method is through the Unit Ops tab of the Workbook.



Workbook Icon

1. Click the **Workbook** icon to ensure the Workbook is active.
2. Click the **Unit Ops** tab of the Workbook.
3. Click the **Add UnitOp** button. The UnitOps view appears, listing all available unit operations.  
When you click the **Add** button or press ENTER inside this view, HYSYS adds the operation that is currently selected.
4. Select Mixer by doing **one** of the following:
  - Start typing 'mixer'.
  - Scroll down the list using the vertical scroll bar, then select Mixer.

Figure 3.45



You can also filter the list by selecting the Piping Equipment radio button in the Categories group, then use one of the above methods to install the operation.

Double-clicking on a listed operation can also be used instead of the Add button or the ENTER key.


5. With Mixer selected, click the **Add** button, or press ENTER.



The property view for the Mixer appears.

The default naming scheme for unit operations can be changed in your Session Preferences.

**Figure 3.46**



The unit operation property view contains all the information required to define the operation, organized into tabs and pages. The Design, Rating, Worksheet and Dynamics tabs appear in the property view for most operations. Property views for more complex operations contain more tabs. HYSYS has provided the default name MIX-100 for the Mixer.

Many operations, like the Mixer, accept multiple feed streams. Whenever you see a table like the one in the Inlets group, the operation will accept multiple stream connections at that location. When the Inlets table is active, you can access a drop-down list of available streams.


Next, you will complete the Connections page for the Mixer.

6. In the Inlets table, click in the <<Stream>> cell. The status indicator at the bottom of the view indicates that the operation needs a feed stream.



7. Open the drop-down list of inlets by clicking on  or by pressing the F2 key then SPACEBAR.


Figure 3.47



Alternatively, you can connect the stream by typing the exact stream name in the <<Stream>> cell, then pressing ENTER.

8. Select Prop Oxide from the drop-down list. The Prop Oxide stream appears in the Inlets table, and <<Stream>> automatically moves down to a new empty cell.
9. In the Inlets table, click the new empty <<Stream>> cell and select Water Feed from the list. The status indicator now displays 'Requires a product stream'.
10. Move to the **Outlet** field by pressing TAB, or by clicking in the cell.
11. Type Mixer Out in the cell, then press ENTER. HYSYS recognizes that there is no existing stream with this name, so it creates the new stream.

Figure 3.48






The status indicator displays a green OK, indicating that the operation and attached streams are completely calculated. The Connections page is now complete.

12. Click the **Parameters** page.
13. In the Automatic Pressure Assignment group, keep the default setting of **Set Outlet to Lowest Inlet**.

**Figure 3.49**



14. Click the **Worksheet** tab in the MIX-100 property view to view the calculated outlet stream. This tab is a condensed Workbook tab displaying only those streams attached to the operation.

HYSYS has calculated the outlet stream by combining the two inlets and flashing the mixture at the lowest pressure of the inlet streams. In this case, both inlets have the same pressure (16.17 psia), so the outlet stream is set to 16.17 psia.

**Figure 3.50**


Name	Prop Oxide	Water Feed	Mixer Out
Vapour	0.0000	0.0000	0.0000
Temperature [F]	75.00	75.00	75.00
Pressure [psia]	16.17	16.17	16.17
Molar Flow [lbmole/hr]	150.0	610.6	760.6
Mass Flow [lb/hr]	8712	1.100e+004	1.971e+004
Std Ideal Liq Vol Flow [USGPM]	20.83	22.01	42.84
Molar Enthalpy [Btu/lbmole]	-5.203e+004	-1.225e+005	-1.086e+005
Molar Entropy [Btu/lbmole-F]	-5.768	1.499	0.8824
Heat Flow [Btu/hr]	-7.804e+006	-7.481e+007	-8.262e+007

15. Close the MIX-100 property view to return to the Workbook.



16. In the Workbook, click the **Unit Ops** tab. The new operation appears in the table.

Figure 3.51



The table shows the operation Name, Object Type, the attached streams (Inlet and Outlet), whether it is Ignored, and its Calc. Level. When you click the View UnitOp button, the property view for the currently selected operation appears. Alternatively, by double-clicking on any cell (except Inlet or Outlet) associated with the operation, you will also open its property view.

You can also open a stream property view directly from the Workbook Unit Ops tab. When any of the cells Name, Object Type, Ignored or Calc. Level are selected, the gray box at the bottom of the view displays all streams attached to the current operation. Currently, the Name cell for MIX-100 has focus, so the box displays the three streams attached to this operation.

For example, to open the property view for the Prop Oxide stream attached to the Mixer, do **one** of the following:

- Double-click on Prop Oxide in the box at the bottom of the view.
- Double-click on the Inlets cell for MIX-100. The property view for the first listed feed stream, in this case Prop Oxide, appears.



# Workbook Features

Before installing the remaining operations, you will examine a number of Workbook features that allow you to access information quickly and change how information is displayed.

## Accessing Unit Operations from the Workbook


While you can easily access the property view for a unit operation from the Unit Ops tab of the Workbook, you can also access operations from the Material Streams, Compositions, and Energy Streams tabs.

Any utilities attached to the stream with focus in the Workbook are also displayed in (and are accessible from) this box.

When your current location is a Workbook streams tab, the gray box at the bottom of the Workbook view displays the operations to which the current stream is attached. For example, click on any cell associated with the stream Prop Oxide. The gray box displays the name of the mixer operation, MIX-100.

If the stream Prop Oxide was also attached to another unit operation, both unit operations would be listed in the box. To access the property view for the Mixer, double-click on its name in the gray box.

Figure 3.52





## Adding a Tab to the Workbook


When the Workbook is active, the Workbook item appears in the HYSYS menu bar. This item allows you to customize the Workbook.

Next you will create a new Workbook tab that displays only stream pressure, temperature, and flow.

1. Do one of the following:
  - From the Workbook menu item, select **Setup**.
  - Object inspect (right-click) the **Material Streams** tab in the Workbook, then select **Setup** from the menu that appears.

The Workbook Setup view appears.

Figure 3.53




The four existing tabs are listed in the Workbook Tabs area. When you add a new tab, it will be inserted before the highlighted tab (currently Material Streams). You will insert the new tab between the Materials Streams tab and the Compositions tab.

2. In the Workbook Tabs list, select Compositions, then click the **Add** button. The New Object Type view appears.




- Click the + beside Stream to expand the tree.

Figure 3.54



- Select Material Stream, then click the **OK** button. You return to the Setup view, and the new tab Material Streams 1 appears after the existing Material Streams tab.
- In the Object group, click in the **Name** field and change the name for the new tab to P,T,Flow to better describe the tab contents.

Figure 3.55






The next task is to customize the tab by removing the variables that are irrelevant.

6. In the Variables table, select the first variable, Vapour Fraction.
7. Press and hold the CTRL key.
8. Select the following variables: Mass Flow, Heat Flow, and Molar Enthalpy.
9. Release the CTRL key.
10. Click the **Delete** button beside the table to remove the selected variables from this Workbook tab only. The finished Setup appears in the figure below.


If you want to remove variables from another tab, you must edit each tab individually.

**Figure 3.56**



11. Close the Setup view. The new tab appears in the Workbook.

**Figure 3.57**



12. Save the case.



## 3.2.7 Installing Equipment on the PFD




PFD Icon

Besides the Workbook, the PFD is the other main view in HYSYS you will use to build the simulation.

To open the PFD, click the PFD icon on the toolbar. The PFD item appears in the HYSYS menu bar whenever the PFD has focus.

When you open the PFD view, it appears similar to the one shown below.

Figure 3.58



Like any other non-modal view, the PFD view can be re-sized by clicking and dragging anywhere on the outside border.

As a graphical representation of your flowsheet, the PFD shows the connections among all streams and operations, also known as “objects”. Each object is represented by a symbol, also known as an “icon”. A stream icon is an arrow pointing in the direction of flow, while an operation icon is a graphic representing the actual physical operation. The object name, also known as a “label”, appears near each icon.

The PFD shown above has been rearranged by moving the Prop Oxide feed stream icon up slightly so it does not overlap the Water Feed stream icon. To move an icon, simply click and drag it to a new location. You can click and drag either the icon (arrow) itself, or the label (stream name), as these two items are grouped together.



Mixer Out	
75.01	F
16.17	psia
760.6	lbmole/hr

Fly-by information



Size Icon



Zoom Out 25%



Display Entire PFD



Zoom In 25%

Other functions that can be performed while the PFD is active include the following:

- Access commands and features through the PFD tool bar.
- Open the property view for an object by double-clicking its icon.
- Move an object by clicking and dragging it to the new location.
- Access “fly-by” summary information for an object by placing the cursor over it.
- Size an object by clicking the Size icon, selecting the object, then clicking and dragging the sizing “handles” that appear.
- Display the Object Inspection menu for an object by placing the cursor over it and right-clicking. This menu provides access to a number of commands associated with the particular object.
- Zoom in and out, or display the entire flowsheet in the PFD window by clicking the zoom buttons at the bottom left of the PFD view.

Some of these functions will be illustrated in this tutorial; for more information, refer to the **User Guide**.

## Calculation Status

HYSYS uses colour-coding to indicate calculation status for objects, both in the object property views, and in the flowsheet. If you recall, the status bar indicator at the bottom of a property view for a stream or operation indicates the current state of the object:

Indicator Status	Description
<b>Red Status</b>	A major piece of defining information is missing from the object. For example, a feed or product stream is not attached to a Separator. The status indicator is red, and an appropriate warning message is displayed.
<b>Yellow Status</b>	All major defining information is present, but the stream or operation has not been solved because one or more degrees of freedom is present. For example, a Cooler whose outlet stream temperature is unknown. The status indicator is yellow, and an appropriate warning message is displayed.
<b>Green Status</b>	The stream or operation is completely defined and solved. The status indicator is green, and an <b>OK</b> message is displayed.

These are the HYSYS default colours; you may change the colours in the Session Preferences.

When you are in the PFD, the streams and operations are colour-coded to indicate their calculation status. If the conditions of an attached stream for an operation were not entirely known, the operation would have a yellow outline indicating its current status. For the Mixer, all streams are defined, so it has no yellow outline.



Notice that the icons for all streams installed to this point are dark blue.

Another colour scheme is used to indicate the status of streams. For material streams, a dark blue icon indicates the stream has been flashed and is entirely known. A light blue icon indicates the stream cannot be flashed until some additional information is supplied. Similarly, a dark red icon is for an energy stream with a known duty, while a purple icon indicates an unknown duty.

## Installing the Reactor

Next, you will install a continuously-stirred-tank reactor operation (CSTR). You can install streams or operations by dropping them from the Object Palette onto the PFD.

1. Ensure that the Object Palette is displayed; if it is not, press F4.
2. You will add the CSTR to the right of the Mixer, so if you need to make some empty space available in the PFD, scroll to the right using the horizontal scroll bar.
3. In the Object Palette, click the CSTR icon.
4. Position the cursor in the PFD to the right of the Mixer Out stream. The cursor changes to a special cursor with a plus (+) symbol attached to it. The symbol indicates the location of the operation icon.




CSTR Icon



Cancel Icon

Figure 3.59



5. Click to “drop” the Reactor onto the PFD. HYSYS creates a new Reactor with a default name, CSTR-100. The Reactor has red status (colour), indicating that it requires feed and product streams.





Attach Mode Icon


When you are in Attach mode, you will not be able to move objects in the PFD. To return to Move mode, click the Attach button again. You can temporarily toggle between Attach and Move mode by holding down the CTRL key.

Multiple connection points appear because the Reactor accepts multiple feed streams.

## Attaching Streams to the Reactor


1. Click the **Attach Mode** icon on the PFD toolbar to enter Attach mode. The Attach Mode button stays active until you click it again.
2. Position the cursor over the right end of the Mixer Out stream icon. A small white box appears at the cursor tip with a pop-up description 'Out', indicating that the stream outlet is available for connection.

Figure 3.60



3. With the pop-up 'Out' visible, click and hold the mouse button. The transparent box becomes solid black, indicating that you are beginning a connection.
4. Move the cursor toward the left (inlet) side of the CSTR-100 icon. A line appears between the Mixer Out stream icon and the cursor, and multiple connection points (blue) appear at the Reactor inlet.
5. Place the cursor near a connection point until a solid white box appears at the cursor tip, indicating an acceptable end point for the connection.

Figure 3.61



6. Release the mouse button, and the connection is made between the stream and the CSTR-100 inlet.
7. Position the cursor over top right-hand corner of the CSTR-100 icon. The white box and the pop-up 'Vapour Product' appear.
8. With the pop-up visible, left-click and hold. The white box again becomes solid black.






Break Connection Icon

If you make an incorrect connection, break the connection and try again.

1. Click the **Break Connection** icon on the PFD tool bar.
2. Place the cursor over the stream line you want to break. The cursor shows a checkmark, indicating an available connection to break.
3. Click once to break the connection.

9. Move the cursor to the right of the CSTR-100. A stream icon appears with a trailing line attached to the CSTR-100 outlet. The stream icon indicates that a new stream will be created when you complete the next step.


Figure 3.62



10. With the stream icon visible, release the left mouse button. HYSYS creates a new stream with the default name 1.
11. Place the cursor over the bottom right connection point on the reactor labeled 'Liquid Product', then click and drag to the right to create the reactor's liquid product stream. The new stream is given the default name 2.
12. Place the cursor over the bottom left connection point on the reactor labeled 'Energy Stream', then click and drag down and to the left to create the reactor's energy stream. The new stream is automatically named Q-100.

The reactor displays a yellow warning status, indicating that all necessary connections have been made, but that the attached streams are not entirely known.

Figure 3.63



13. Click the **Attach Mode** icon again to return to Move mode.
14. Double-click the stream icon 1 to open its property view.
15. In the **Stream Name** cell, enter the new name Reactor Vent, then close the property view.
16. Double-click the stream 2 icon. Rename this stream Reactor Prods, then close the property view.
17. Double-click the Q-100 icon, rename it Coolant, then close the view.


The reactor outlet and energy streams are unknown at this point, so they are light blue and purple, respectively.



## Completing the Reactor Specifications

1. Double-click the CSTR-100 icon to open its property view.
2. Click the Design tab, then select the Connections page (if required). The names of the Inlet, Outlet and Energy streams that were attached before appear in the appropriate cells.
3. In the **Name** cell, change the operation name to Reactor.

Figure 3.64




4. Select the **Parameters** page. For now, the **Delta P** and the **Volume parameters** are acceptable at the default values.




5. Select the **Cooling** radio button. This reaction is exothermic (produces heat), so cooling is required.

Figure 3.65



6. Click the **Reactions** tab. Next you will attach the Reaction Set that you created in the Basis Environment.
7. From the Reaction Set drop-down list, select Set-1. The completed **Reactions** tab appears below.

Figure 3.66



The next task is to specify the Vessel Parameters. In this Tutorial, the reactor has a volume of 280 ft<sup>3</sup> and is 85% full.



- Figure 3.67**



**Figure 3.68**

3-53




At this point, the Reactor product streams and the energy stream Coolant are unknown because the Reactor has one degree of freedom. At this point, either the outlet stream temperature or the cooling duty can be specified. For this example, you will specify the outlet temperature.

Initially the Reactor is assumed to be operating at isothermal conditions, therefore the outlet temperature is equivalent to the feed temperature, 75°F

12. In the Reactor Prods column, click in the **Temperature** cell. Type 75, then press ENTER. HYSYS solves the Reactor.

Figure 3.69



The screenshot shows the 'Worksheet' tab for 'Reactor - Set-1'. The table displays various properties for four streams: Mixer Out, Reactor Prods, Reactor Vent, and Coolant. The 'Temperature [F]' for the Reactor Prods stream is highlighted and set to 75.00.


	Mixer Out	Reactor Prods	Reactor Vent	Coolant
Name				
Vapour	0.0000	0.0000	1.0000	<empty>
Temperature [F]	75.00	75.00	75.00	<empty>
Pressure [psia]	16.17	16.17	16.17	<empty>
Molar Flow [lbmole/hr]	760.6	700.2	0.0000	<empty>
Mass Flow [lb/hr]	1.971e+004	1.971e+004	0.0000	<empty>
Std Ideal Liq Vol Flow [USGPM]	42.84	41.10	0.0000	<empty>
Molar Enthalpy [Btu/lbmole]	-1.086e+005	-1.214e+005	-5.030e+004	<empty>
Molar Entropy [Btu/lbmole-F]	0.8824	0.6769	20.68	<empty>
Heat Flow [Btu/hr]	-8.262e+007	-8.499e+007	0.0000	-2.372e+006

There is no phase change in the Reactor under isothermal conditions since the flow of the vapour product stream Reactor Vent is zero. In addition, the required cooling duty has been calculated and is represented by the Heat Flow of stream Coolant. The next step is to examine the Reactor conversion as a function of temperature.



13. Click the **Reactions** tab, then select the **Results** page. The conversion appears in the Reactor Results Summary table.


Figure 3.70



Under the current conditions, the Actual Percent Conversion (Act.% Cnv.) in the Reactor is 40.3%. You will adjust the Reactor temperature until the conversion is in the 85-95% range.

14. Click the **Worksheet** tab.
15. In the Reactor Prods column, change the **Temperature** to 100°F
16. Return to the **Reactions** tab to check the conversion, which has increased to 72.28% as shown below.

Figure 3.71




17. Return to the **Worksheet** tab, and change the **Temperature** of Reactor Prods to 140°F



- Click the **Reactions** tab again and check the conversion. The conversion at 140°F is approximately 95%, which is acceptable.

Figure 3.72



Reaction Results Summary			
	<input checked="" type="radio"/> Reaction Extents	<input type="radio"/> Reaction Balance	
	Act. % Conv.	Base Comp	Rxn Extent
Rxn-1	94.70	12C3Oxide	142.0

- Close the Reactor property view.

## Installing the Column

HYSYS has a number of pre-built column templates that you can install and customize by changing attached stream names, number of stages and default specifications. For this example, a Distillation Column will be installed.

- Before installing the column, click the **Tools** menu and select **Preferences**. On the **Simulation** tab, click on the **Options** page and ensure that the **Use Input Experts** checkbox is selected (checked), then close the view.
- Double-click the **Distillation Column** icon on the Object Palette.




Distillation Column Icon

The Input Expert is a logical sequence of input views that guide you through the initial installation of a Column. Complete the steps to ensure that you have provided the minimum amount of information required to define the column.

The Input Expert is a Modal view, indicated by the absence of the Maximize/Minimize icons. You cannot exit or move outside the Expert until you supply the necessary information, or click the **Cancel** button.

Figure 3.73



**Distillation Column Input Expert**

Condenser Energy Stream: [Dropdown]

Column Name: T-100

Inlet Streams:

Stream	Inlet Stage
<< Stream >>	

# Stages: n = 10

Optional Side Draws:

Stream	Type	Draw Stage
<< Stream >>		

Reboiler Energy Stream: [Dropdown]

Bottoms Liquid Outlet: [Dropdown]

Water Draw: ☐

Stage Numbering: ☒ Top Down ☐ Bottom Up

< Prev Next >

Connections (page 1 of 4) Cancel



When you install a column using a pre-built template, HYSYS supplies certain default information, such as the number of stages. The **Numb of Stages** field contains **10** (default number of stages). Note the following:

- These are theoretical stages, as the HYSYS default stage efficiency is one.
- The Condenser and Reboiler are considered separate from the other stages, and are not included in the Num of Stages field.

3. For this example, 10 theoretical stages are used, so leave the **Numb of Stages** at its default value.
4. In the Inlet Streams table, click in the <<Stream>> cell.
5. From the drop-down list of available inlet streams, select **Reactor Prods** as the feed stream to the column. HYSYS supplies a default feed location in the middle of the Tray Section (TS), in this case stage 5 (indicated by 5\_Main TS).
6. In the **Condenser** group, ensure the **Partial** radio button is selected, as the column will have both Vapour and Liquid Overhead Outlets.
7. In the **Column Name** field, change the name to Tower.
8. In the **Condenser Energy Stream** field, type CondDuty, then press ENTER.
9. In the top **Ovhd Outlets** field, type OvhdVap, then press ENTER. In the bottom **Ovhd Outlets** field, type RecyProds, then press ENTER.
10. In the **Reboiler Energy Stream** field, type RebDuty, then press ENTER.
11. In the **Bottoms Liquid Outlet** field, type Glycol, then press ENTER.

When you are finished, the Next button becomes active, indicating sufficient information has been supplied to advance to the next page of the Input Expert. The first page of the Input Expert should appear as shown in the following figure.

Figure 3.74

**Distillation Column Input Expert**

Condenser Energy Stream:

Column Name:

Inlet Streams:

Stream	Inlet Stage
Reactor Prods	5_Main
<< Stream >>	

# Stages:

Stage Numbering: ☒ Top Down ☐ Bottom Up

Condenser: ☒ Total ☒ Partial ☐ Full Reflux

Ovhd Outlets:

Optional Side Draws:

Stream	Type	Draw Stage
<< Stream >>		

Reboiler Energy Stream:

Bottoms Liquid Outlet:

< Prev Next >


Connections (page 1 of 4) Cancel

12. Click the **Next** button to advance to the **Pressure Profile** page.



13. In the **Condenser Pressure** field, enter 15 psia.  
In the **Reboiler Pressure** field, enter 17 psia.  
Leave the **Condenser Pressure Drop** at its default value of zero.

Figure 3.75



Although HYSYS does not require estimates to produce a converged column, you should provide estimates for columns that are difficult to converge.

14. Click the **Next** button to advance to the **Optional Estimates** page. For this example, no estimates are required.
15. Click the **Next** button to advance to the fourth and final page of the Input Expert. This page allows you to supply values for the default column specifications that HYSYS has created.


In general, a Distillation Column has three default specifications. The overhead Vapour Rate and Reflux Ratio will be used as active specifications, and later you will create a glycol purity specification to exhaust the third degree of freedom. The third default specification, overhead Liquid Rate, will not be used.



The Flow Basis applies to the Vapour Rate, so leave it at the default of Molar.


16. In the **Vapour Rate** field, enter 0 lbmole/hr.  
In the **Reflux Ratio** field, enter 1.0.

Figure 3.76



17. Click the **Done** button. The Column property view appears.
18. On the **Design** tab, select the **Monitor** page.

Figure 3.77



You can also change specification values, and activate or de-activate specifications used by the Column solver directly from the Monitor page.

The Monitor page displays the status of your column as it is being calculated, updating information with each iteration.



## Adding a Column Specification

The current Degrees of Freedom is zero, indicating the column is ready to be run, however, the Distillate Rate (Overhead Liquid Rate for which no value was provided in the Input Expert) is currently an Active specification with a Specified Value of <empty>. For this example, you will specify a water mole fraction of 0.005 in the Glycol product stream.

1. Since it is not desirable to use this specification, clear the **Active** checkbox for the Distillate Rate. The Degrees of Freedom increases to 1, indicating that another active specification is required.
2. On the **Design** tab, select the **Specs** page.
3. In the Column Specifications group, click the **Add** button. The Add Specs view appears.
4. Select Column Component Fraction as the Specification Type.
5. Click the **Add Spec(s)** button. The Comp Frac Spec view appears.






Figure 3.78



6. In the **Name** cell, change the name to H2O Fraction.
7. In the **Stage** cell, select Reboiler from the drop-down list.


Figure 3.79





8. In the **Spec Value** cell, enter 0.005 as the liquid mole fraction specification value.
9. In the Components list, click in the first cell labeled <<Component>>, then select H<sub>2</sub>O from the drop-down list of available components.


Figure 3.80



10. Close this view to return to the Column property view. The new specification appears in the Column Specifications list on the **Specs** page.
11. Return to the **Monitor** page, where the new specification appears at the bottom of the Specifications list.
12. Click the **Group Active** button to bring the new specification to the top of the list, directly under the other Active specifications.

If you want to view the entire Specifications table, re-size the view by clicking and dragging its bottom border.

Figure 3.81






HYSYS automatically made the new specification Active when you created it.

The Degrees of Freedom has returned to zero, so the column is ready to be calculated.

## Running the Column

1. Click the **Run** button to begin calculations, and the information displayed on the page is updated with each iteration. The column converges quickly, in five iterations.

Figure 3.82




The converged temperature profile appears in the upper right corner of the view.

2. Select the **Press** or **Flow** radio button to view the pressure or flow profiles.



- To access a more detailed stage summary, click the **Performance** tab, then select the **Column Profiles** page.

Figure 3.83



## Accessing the Column Sub-flowsheet

When considering the column, you might want to focus only on the column sub-flowsheet. You can do this by entering the column environment.



PFD Icon



Workbook Icon



Column Runner Icon

- Click the **Column Environment** button at the bottom of the property view. While inside the column environment, you can do the following:
  - View the column sub-flowsheet PFD by clicking the **PFD** icon.
  - View a Workbook of the column sub-flowsheet objects by clicking the **Workbook** icon.
  - Access the "inside" column property view by clicking the **Column Runner** icon. This property view is essentially the same as the "outside", or Main Flowsheet, property view of the column.



The column sub-flowsheet PFD and Workbook appear in the following figures.

Figure 3.84




Figure 3.85

Name	Reflux	To Condenser	Boilup	To Reboiler	OvhdVap
Vapour Fraction	0.0000	1.0000	1.0000	0.0000	1.0000
Temperature [F]	159.0	212.2	375.7	360.0	159.0
Pressure [psia]	15.00	15.00	17.00	17.00	15.00
Molar Flow [lbmole/hr]	475.8	951.6	817.8	960.6	4.369e-005
Mass Flow [lb/hr]	8890	1.778e+004	6.006e+004	7.088e+004	2.006e-003
Liquid Volume Flow [USGPM]	17.97	35.94	115.4	136.1	4.701e-006
Heat Flow [Btu/hr]	-5.700e+007	-9.656e+007	-1.393e+008	-1.869e+008	-2.534
Name	RecyProds	Glycol	Reactor Prods	** New **	
Vapour Fraction	0.0000	0.0000	0.0000		
Temperature [F]	159.0	375.7	140.0		
Pressure [psia]	15.00	17.00	16.17		
Molar Flow [lbmole/hr]	475.8	142.8	618.5		
Mass Flow [lb/hr]	8890	1.082e+004	1.971e+004		
Liquid Volume Flow [USGPM]	17.97	20.78	38.75		
Heat Flow [Btu/hr]	-5.700e+007	-2.803e+007	-8.714e+007		

**Material Streams** Compositions Energy Streams Unit Ops

Main TS  
Condenser

☐ Show Name Only  
Number of Hidden Objects: 0



Enter Parent Simulation  
Environment Icon

- When you are finished in the column environment, return to the Main Flowsheet by clicking the **Enter Parent Simulation Environment** icon.
- Open the PFD for the Main Flowsheet and select **Auto Position All** from the **PFD** menu. HYSYS arranges your PFD in a logical manner.




### Moving Objects and Labels in a PFD

The PFD below has been customized by moving some of the stream icons. To move an icon, simply click and drag it to the new location.

You can also move a stream or operation label (name).

1. Right-click on the label you want to move.
2. From the menu that appears, select **Move/Size Label**. A box appears around the label.
3. Click and drag the label to a new location, or use the arrow keys to move it.

**Figure 3.86**






## 3.2.8 Viewing Results

1. Click the **Workbook** icon to access the calculated results for the Main Flowsheet.

The Material Streams tab and Compositions tab of the Workbook appears below.

Figure 3.87





## Using the Object Navigator

If you want to view the calculated properties of a particular stream or operation, you can use the Object Navigator to quickly access the property view for any stream or unit operation at any time during the simulation.

To open the Navigator, do **one** of the following:


- Press **F3**.
- From the Flowsheet menu, select **Find Object**.
- Double-click on any blank space on the HYSYS Desktop.
- Click the **Navigator** icon.



Navigator Icon

The Object Navigator view appears.

Figure 3.88



You can control which objects appear by selecting a different Filter radio button. For example, to list all streams and unit operations, select the **All** button.

The UnitOps radio button in the Filter group is currently selected, so only the Unit Operations appear in the list of objects.

To open a property view, select the operation in the list, then click the View button or double-click on the operation name.

You can also search for an object by clicking the Find button.

When the Find Object view appears, enter the object name, then click the OK button. HYSYS opens the property view for the object you specified

You can start or end the search string with an asterisk (\*), which acts as a wildcard character. This lets you find multiple objects with one search. For example, searching for VLV\* will open the property view for all objects with VLV at the beginning of their name.




## Using the Databook

The HYSYS Databook provides you with a convenient way to examine your flowsheet in more detail. You can use the Databook to monitor key variables under a variety of process scenarios, and view the results in a tabular or graphical format.

1. Before opening the Databook, close the Object Navigator and any property views you might have opened using the Navigator.
2. To open the Databook, do **one** of the following:
  - Press **CTRL D**.
  - From the **Tools** menu, select **Databook**.

The Databook view appears.

Figure 3.89



To edit any of the Objects in the Databook:

1. Select the Object you want to edit.
2. Click the **Edit** button.

The first task is to add key variables to the Databook. For this example, the effects of the Reactor temperature on the Reactor cooling duty and Glycol production rate will be examined.


3. On the **Variables** tab, click the **Insert** button. The Variable Navigator appears.
4. In the Object Filter group, select the **UnitOps** radio button. The Object list is filtered to show unit operations only.
5. In the Object list, select Reactor. The variables available for the Reactor object appear in the Variable list.



The Variable Navigator is used extensively in HYSYS for locating and selecting variables. The Navigator operates in a left-to-right manner—the selected Flowsheet determines the Object list, the chosen Object dictates the Variable list, and the selected Variable determines whether any Variable Specifics are available.


- In the Variable list, select Vessel Temperature. Vessel Temperature appears in the **Variable Description** field. You can edit the default variable description.

Figure 3.90



- In the **Variable Description** field, rename the variable Reactor Temp, then click the **OK** button. The variable now appears in the Databook.

Figure 3.91




- To add the next variable, click the **Insert** button. The Variable Navigator appears.
- In the Object Filter group, select the **Streams** radio button. The Object list is filtered to show streams only.
- In the Object list, select Coolant in the Object list. The variables available for this stream appear in the Variable list.




11. In the Variable list, select Heat Flow.

Figure 3.92



12. In the **Variable Description** field, change the description to Cooling Duty, then click the OK button. The variable now appears in the Databook.
13. Click the **Insert** button again. In the Object list, select Glycol. In the Variable list, select Liq Vol Flow@Std Cond. Change the **Variable Description** for this variable to Glycol Production, then click the OK button. The completed **Variables** tab of the Databook appears below.

Figure 3.93



Now that the key variables have been added to the Databook, the next task is to create a data table in which to display these variables.


14. Click the **Process Data Tables** tab.



The three variables that you added to the Databook appear in the table on this tab.


15. In the Available Process Data Tables group, click the **Add** button. HYSYS creates a new table with the default name ProcData1.

Figure 3.94




16. In the **Process Data Table** field, change the name to Key Variables.
17. In the Show column, activate each variable by clicking on the corresponding checkbox.

Figure 3.95



18. Click the **View** button to view the new data table.

Figure 3.96



This table will be accessed again later to demonstrate how its results are updated whenever a flowsheet change is made.


19. For now, click the **Minimize** icon in the upper right corner of the Key Variables Data view. HYSYS reduces the view to an icon and places it at the bottom of the Desktop.



Before you make changes to the flowsheet, you will record the current values of the key variables. Instead of manually recording the variables, you can use the Data Recorder to automatically record them for you.

20. Click the **Data Recorder** tab in the Databook.


Figure 3.97



When using the Data Recorder, you first create a Scenario containing one or more of the key variables, then record the variables in their current state.

21. In the Available Scenarios group, click the **Add** button. HYSYS creates a new scenario with the default name Scenario 1.
22. In the Data Recorder Data Section group, activate each variable by clicking on the corresponding **Include** checkbox.

Figure 3.98









23. Click the **Record** button to record the variables in their current state. The New Solved State view appears, prompting you for the name of the new state.
24. In the **Name for New State** field, change the name to Base Case, then click **OK**. You return to the Databook.
25. In the Available Display group, select the **Table** radio button, then click the **View** button. The Data Recorder view appears, showing the values of the key variables in their current state.

Figure 3.99



Now you can make the necessary flowsheet changes and these current values remain as a permanent record in the Data Recorder unless you choose to erase them.

26. Click the **Minimize** icon on the Data Recorder view.
27. Click the **Restore Up** icon  on the Key Variables Data title bar to restore the view to its regular size.

Next, you will change the temperature of stream Reactor Prods (which determines the Reactor temperature), then view the changes in the process data table




Navigator Icon

28. Click the **Navigator** icon in the toolbar.
29. In the Filter group, select the **Streams** radio button.
30. In the Streams list, select Reactor Prods, then click the **View** button. The Reactor Prods property view appears.
31. Ensure you are on the **Worksheet** tab, **Conditions** page of the property view.



32. Arrange the Reactor Prods and Key Variables Data views so you can see them both.


Figure 3.100



Currently, the Reactor temperature is 140°F. The key variables will be checked at 180°F.

33. In the Reactor Prods property view, change the value in the **Temperature** cell to 180. HYSYS automatically recalculates the flowsheet. The new results appears below.

Figure 3.101





34. Click the **Close** button on the Reactor Prods stream property view to return to the Databook. You can now record the key variables in their new state.
35. Click on the **Data Recorder** tab in the Databook.
36. Click the **Record** button. The New Solved State view appears.
37. In the **Name for New State** field, change the name to 180F Reactor, then click the **OK** button.
38. In the Available Display group, click the **View** button. The Data Recorder appears, displaying the new values of the variables.

[illegible]

This completes the HYSYS Chemicals Steady State Simulation tutorial. If there are any aspects of this case that you would like to explore further, feel free to continue working on this simulation on your own.

For other chemical case examples, see the Applications section. Applications beginning with “C” explore some of the types of chemical simulations that can be built using HYSYS.



## 3.3 Dynamic Simulation

In this tutorial, the dynamic capabilities of HYSYS will be incorporated into a basic steady state chemicals model. In the steady state simulation, a continuously-stirred tank reactor (CSTR) converted propylene oxide and water into propylene glycol. The reactor products were then fed into a distillation tower where the glycol product was recovered in the tower bottoms.

A completed dynamic case has been pre-built and is located in the file **DynTUTOR3.hsc** in your HYSYS\Samples directory.


This tutorial follows these basic steps for setting up a dynamic simulation case:

1. Obtain a simplified steady state model to be converted to dynamic mode.
2. Use the Dynamic Assistant to set pressure-flow specifications, modify the flowsheet topology, and size the equipment.
3. Modify the Reactor vent stream to account for reverse flow conditions.
4. Set up temperature and level controllers around and in the Reactor vessel.
5. Set up the Databook. Make changes to key variables in the process and observe the dynamic behaviour of the model.

The dynamic simulation will take the steady state CSTR simulation case and convert it into dynamic mode. If you have not built the simulation for the steady state simulation, you can open the pre-built case included with your HYSYS package.

A flowsheet of the completed dynamic simulation is shown in the figure below.

Figure 3.103



Only the CSTR reactor will be converted to dynamic mode. The Column operation will be deleted from the simulation flowsheet.

The Dynamics Assistant will be used to make pressure-flow specifications, modify the flowsheet topology, and size pieces of equipment in the simulation flowsheet. This is only **one** method of preparing a steady state case for dynamic mode. It is also possible to set your own pressure-flow specifications and size the equipment without the aid of the Dynamic Assistant.



## 3.3.1 Simplifying the Steady State Flowsheet

The distillation column in the Chemicals Tutorial will be deleted in this section.


1. Open the pre-built case file **TUTOR3.hsc** located in your HYSYS\Samples directory (if you are not continuing from the Steady State Simulation section of this tutorial).
2. From the **Tools** menu, select **Preferences**.
3. Click the **Variables** tab, then select the **Units** page.
4. In the Available Unit Sets group, select Field. Close the Session Preferences view.
5. From the **File** menu, select **Save As**. Save the case as **DynTUT3-1.hsc**.
6. Delete all material streams and unit operations downstream of the Reactor Prods stream. The following 6 items should be deleted:

When you delete a stream, unit or logical operation from the flowsheet, HYSYS will ask you to confirm the deletion. To delete the object, click the **Yes** button. If not, click the **No** button.

Material Streams	Energy Streams	Unit Operations
Ovhd Vap RecyProds Glycol	CondDuty RebDuty	Tower

7. The steady state simulation case should solve with the deletion of the above items. The PFD for the dynamic tutorial should appear as shown below.

Figure 3.104



Before entering dynamics, the pressure specification on the Water Feed stream should be removed so that the MIX-100 unit operation can calculate its pressure based on the Prop Oxide stream specification.

8. Double-click the Water Feed stream icon to open its property view.
9. On the **Conditions** page of the **Worksheet** tab, click in the **Pressure** cell, then press DELETE.




10. Close the Water Feed stream property view.
11. Double-click the MIX-100 icon to open its property view.
12. Click the **Design** tab, then select the **Parameters** page.
13. In the Automatic Pressure Assignment group, select the **Equalize All** radio button. HYSYS solves for the stream and mixer operation.
14. Close the mixer property view.
15. Save the case.

## 3.3.2 Using the Dynamics Assistant

The Dynamics Assistant makes recommendations as to how the flowsheet topology should change and what pressure-flow specifications are required in order to run a case in dynamic mode. In addition, it automatically sets the sizing parameters of the equipment in the simulation flowsheet. Not all the suggestions the Dynamics Assistant offers need to be followed.

Figure 3.105



The Dynamics Assistant will be used to do the following:


- Add Pressure Flow specifications to the simulation case.
- Add Valves to the Boundary Feed and Product streams.
- Size the Valve, Vessel, and Heat Exchange operations.



For this tutorial, the Session Preferences will be set so that the Dynamics Assistant will not manipulate the dynamic specifications.

1. Open the **Tools** menu and select **Preferences**. The Session Preferences view appears.
2. Click the **Simulation** tab, then select the **Dynamics** page.
3. Ensure that the **Set dynamic stream specifications in the background** checkbox is cleared.

**Figure 3.106**



4. Close the Session Preference view, then close all open views on the HYSYS desktop except for the PFD view.



Dynamic Assistant icon

Next, you will initiate the Dynamics Assistant to evaluate the specifications required to run in dynamic simulation.

5. Click the **Dynamics Assistant** icon. Browse through each tab in the Dynamic Assistant view to inspect the recommendations.



An **Active** recommendation will be implemented by the Dynamic Assistant.

All recommendations in the Dynamic Assistant will be implemented by default unless you deactivate them. You can choose which recommendations will be executed by the Dynamic Assistant by activating or deactivating the OK checkboxes beside each recommendation.




An **Inactive** recommendation will not be implemented by the Dynamic Assistant.



- Click the **Streams** tab. The Streams tab contains a list of recommendations regarding the setting or removing of pressure-flow specifications in the flowsheet.

Figure 3.107



- For each page in the **Streams** tab, activate or deactivate the following recommendations.

Page	Recommendation	Stream	OK Checkbox
Pressure Specs	Remove Pressure Specifications	Prop Oxide	Active
Flow Specs	Remove Flow Specifications	Prop Oxide	Active
		Water Feed	Active
Insert Valves	Insert Valves	Prop Oxide	Active
		Reactor Prods	Active
		Reactor Vent	Inactive
		Water Feed	Active

The Dynamics Assistant will insert valves on all the boundary flow streams except the Reactor Vent stream. This recommendation was deactivated since it is assumed that the CSTR reactor is exposed to the open air. Therefore, the pressure of the reactor is constant. A constant pressure can be modeled in the CSTR reactor by setting the Reactor Vent stream with a pressure specification. A valve should not be inserted on this stream.



8. Click the **Other** tab. This tab contains a list of miscellaneous changes that should be made in order for the Dynamic simulation case to run effectively. Activate the following recommendations if required:

Page	Recommendation	Unit Operation	OK Checkbox
Misc Specs	Set Equalize Option Mixers	MIX-100	Active

9. Click the **Make Changes** button once only. All the active suggestions in the Dynamics Assistant are implemented. Close the Dynamics Assistant view.
10. Switch to Dynamic mode by pressing the **Dynamic Mode** icon.



Dynamic Mode Icon

When asked if you want to let the dynamics assistant evaluate your process before moving into dynamics, click the **No** button.


Since the suggestion to insert a valve on the Reactor Vent stream was deactivated, you must set a pressure specification on this stream.

11. Double-click the Reactor Vent stream icon in the PFD. The property view appears.
12. Click the **Dynamics** tab, then select the **Specs** page.
13. In the Pressure Specification group, click in the **Active** checkbox to activate the specification.
14. Close the Reactor Vent stream property view.

**In order for the CSTR to operate in steady state and dynamic mode, the vessel must be specified with a volume. Since the Dynamic Assistant detected that a volume was already specified for the CSTR reactor, it did not attempt to size it.**

15. The PFD for the dynamic tutorial (before the addition of the controllers) should look like the following figure.

Figure 3.108



16. Save the case as **DynTUT3-2.hsc**.



### 3.3.3 Modeling a CSTR Open to the Atmosphere

The CSTR reactor is open to the atmosphere and the liquid level of the reactor can change in dynamic mode. This means that the vapour space in the liquid reactor also varies with the changing liquid level. In order to model this effect, the Reactor Vent stream was set with a constant pressure specification. However, one additional modification to the Reactor Vent stream is required.

Since the liquid level in the CSTR can move up and down, regular and reverse flow can be expected in the Reactor Vent stream. When vapour exits the reactor vessel (regular flow), the composition of the Reactor Vent stream is calculated from the existing vapour in the vessel. When vapour enters the vessel (reverse flow), the composition of the vapour stream from the atmosphere must be defined by the Product Block attached to the Reactor Vent stream. It is therefore necessary to specify the Product Block composition.

The original steady state Chemicals tutorial used a Fluid Package which did not include any inert gases. Therefore, it is now necessary to return to the Simulation Basis Manager and add the required components to the Fluid Package.




Enter Basis Environment icon

The Simulation Basis Manager allows you to create, modify, and otherwise manipulate Fluid Packages in the simulation case.

1. Click the **Enter Basis Environment** icon. The Simulation Basis Manager view appears.
2. Click the **Fluid Pkgs** tab. In the Current Fluid Packages group, the Fluid Package associated with the Chemical Tutorial appears.


Figure 3.109






3. In the Current Fluid Packages group, select the fluid package, then click the **View** button. The Fluid Package: Basis-1 property view appears.

Figure 3.110



4. Click the **Setup** tab. In the Component List Selection group, click the **View** button. The Component List View appears.

Figure 3.111



5. In the Components Available group, select the **FullName/Synonym** radio button.




6. In the **Match** field, start typing Nitrogen. HYSYS filters the component list to match your input.
7. When Nitrogen is selected in the list, press the ENTER key. Nitrogen is added to the Selected Components List. Close the Component List view.
8. Close the Fluid Package: Basis-1 property view.
9. In the Simulation Basis Manager view, click on the **Return to Simulation Environment** button.
10. On the PFD, double-click the **Reactor Vent** stream icon to open its property view.
11. Click the **Product Block** button or the **View Downstream Operation** icon. The Product Block view appears.



View Downstream Operation icon

Figure 3.112




12. Click the **Composition** tab.
13. In the Compositions table, specify the composition of the reverse flow stream as follows:

Component	Mole Fraction
12C3Oxide	0.0
12-C3diol	0.0
H2O	0.0
Nitrogen	1.0

14. Click the **Conditions** tab.



15. In the Flow Reversal Conditions group, select the **Temperature** radio button.
16. In the field beside the Temperature radio button, enter 77 °F. These stream conditions will be used to flash the pure nitrogen stream when the Reactor Vent flow reverses.

**Figure 3.113**

17. Close the ProductBlock\_Reactor Vent view.
18. Close the Reactor Vent stream property view.
19. Save the case as **DynTUT3-3.hsc**.



## 3.3.4 Adding Controller Operations

In this section you will identify and implement key control loops using PID Controller logical operations. Although these controllers are not required to run in dynamic mode, they will increase the realism of the model and provide more stability.

### Level Control

First you will install a level controller to control the liquid level in the CSTR Reactor operation.




Control Ops icon



PID Controller icon

1. Press **F4** to activate the Object Palette, if required.
1. In the Object Palette, click the **Control Ops** icon. A sub-palette appears.
2. In the sub-palette, click the **PID Controller** icon. The cursor changes to include a frame and a + sign.
3. In the PFD, click near the Reactor icon. The IC-100 icon appears. This controller will serve as the Reactor level controller.
4. Double-click the IC-100 icon. The controller's property view appears.


Figure 3.114






5. In the **Connections** tab, click in the **Name** field and change the name to Reactor LC.
6. In the Process Variable Source group, click the **Select PV** button. The Select Input PV view appears.
7. In the Object group list, select Reactor.  
In the Variable list, select Liquid Percent Level.  
Click the **OK** button.

Figure 3.115



8. In the Output Target Object group, click the **Select OP** button. The Select OP Object view appears.
9. In the Object list, select VLV-Reactor Prods, then click the **OK** button.

Figure 3.116




10. Click the **Parameters** tab, then select the **Configuration** page.



11. On this page, enter the following information:

In this cell...	Enter...
Action	Direct
Kc	2
Ti	10 minutes
PV Minimum	0%
PV Maximum	100%



12. Click the **Face Plate** button at the bottom of the property view. The Reactor LC face plate view appears.
13. From the drop-down list, select Auto to change the controller mode.
14. Double-click in the PV value field, type 85, then press ENTER.
15. Close the Reactor LC face plate view, then close the Reactor LC property view.

## Flow Control

Next you will add flow controllers to the feed streams in the process.



Control Ops icon



PID Controller icon

1. The Control Ops sub-palette should still be open. If it isn't, click the **Control Ops** icon in the Object Palette.
2. In the sub-palette, click the **PID Controller** icon.
3. In the PFD, click above the Prop Oxide stream icon. The IC-100 icon appears. This controller will serve as the Prop Oxide flow controller.
4. Double-click the IC-100 icon to open its property view.
5. Specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	PropOxide FC
	Process Variable Source	Prop Oxide, Mass Flow
	Output Target Object	VLV-Prop Oxide
<b>Parameters [Configuration]</b>	Action	Reverse
	Kc	0.1
	Ti	5 minutes
	PV Minimum	0 lb/hr
	PV Maximum	18,000 lb/hr

6. Click the **Face Plate** button. Change the controller mode to Auto, and input a set point of 8712 lb/hr.



7. Close the PropOxide FC face plate view and property view.
8. In the Object sub-palette, click the **PID Controller** icon.
9. In the PFD, click below the Water Feed stream icon. The controller icon appears. This controller will serve as the Water Feed flow controller.
10. Double-click the controller icon, then specify the following details:

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	WaterFeed FC
	Process Variable Source	Water Feed, Mass Flow
	Output Target Object	VLV-Water Feed
<b>Parameters [Configuration]</b>	Action	Reverse
	Kc	0.1
	Ti	5 minutes
	PV Minimum	0 lb/hr
	PV Maximum	22,000 lb/hr

11. Click the **Face Plate** button. Change the controller mode to Auto and input a set point of 11,000 lb/hr.
12. Close the WaterFeed FC face plate view and property view.

## Temperature Control

Next you will install temperature controller to control the temperature of the CSTR reactor. The control will be implemented using an energy utility stream.

1. In the Object sub-palette, click the **PID Controller** icon, then click in the PFD above and to the left of the Reactor icon. The controller icon appears. This controller will serve as the Reactor temperature controller.




- Double-click the controller icon, then specify the following details.

Tab [Page]	In this cell...	Enter...
<b>Connections</b>	Name	Reactor TC
	Process Variable Source	Reactor, Vessel Temperature
	Output Target Object	Coolant
<b>Parameters [Configuration]</b>	Action	Direct
	Kc	1.75
	Ti	5 minutes
	PV Minimum	70°F
	PV Maximum	300°F

- Click the **Control Valve** button. The FCV for Coolant view appears.

Figure 3.117



- In the Duty Source group, select the **Direct Q** radio button.
- In the Direct Q group table, enter the following information

In this cell...	Enter...
<b>Minimum Available</b>	0 Btu/hr
<b>Maximum Available</b>	$1 \times 10^7$ Btu/hr

- Close the FCV for Coolant view.
- Click the **Face Plate** button. Change the controller mode to Auto and input a set point of 140 °F
- Close the Reactor TC face plate view and property view.
- Save the case as **DynTUT3-4.hsc**.






Integrator icons  
Green=Active  
Red=Holding

10. The integrator can be run at this point. Click the **Integrator Active** icon in the tool bar.
11. When you are given the option to run the dynamic assistant first before running the integrator, click the **No** button.

When the integrator is initially run, HYSYS will detect that the Reactor does not have a vapour phase at the specified process conditions. You have the option to select either the default, which is to Increase Temperature, or choose 100% Liquid in the Reactor.

Figure 3.118



12. Select the default setting, which is **Increase Temperature**.
13. Let the integrator run for a while, then click the **Integrator Holding** icon to stop the Integrator.

At this point you can make changes to key variables in the process then observe the changes in the dynamic behaviour of the model.

Next you will monitor important variables in dynamics using strip charts.




## 3.3.5 Monitoring in Dynamics

Now that the model is ready to run in dynamic mode, you will create a strip chart to monitor the general trends of key variables.

Add all of the variables that you would like to manipulate or model. Include feed and energy streams that you want to modify in the dynamic simulation.


1. Open the Databook by using the hot key combination CTRL D. The following is a general procedure to install strip charts in HYSYS.

Figure 3.119



2. On the **Variables** tab, click on the **Insert** button. The Variable Navigator appears.

Figure 3.120






Select the Flowsheet, Object and Variable for any of the suggested variables. For Reactor Prods also select the Variable Specifics indicated. A list of suggested variables appears below:

Variables to Manipulate	
Object	Variable
Prop Oxide	Mass Flow
Water Feed	Mass Flow

Variables to Monitor		
Object	Variable	Variable Specifics
Reactor	Vessel Temperature	
Reactor Prods	Comp Molar Flow	12C3Oxide
Rector	Liquid Percent Level	

- Click on the **OK** button to return to the Databook. The variable will now appear on the **Variables** tab.
- Repeat the procedure to add all remaining variables to the Databook.
- Click the **Strip Charts** tab in the Databook view.

Figure 3.121




- Click the **Add** button. HYSYS will create a new strip chart with the default name DataLogger1.
- In the **Logger Name** field, change the name to Key Variables1.



8. Click the **Active** checkbox for each of the variables that you would like to monitor. Keep the number of variables per Strip Chart to four or fewer, for easier viewing.

Figure 3.122



You can change the configuration of each strip chart by clicking the Setup button.

9. If required, add more strip charts.
10. Click the **Strip Chart** button to view each strip chart.
11. Click the **Start Integrator** icon and observe as the variables line out. If you see a warning regarding the Dynamics Assistant, click the **No** button. When you are finished, click the **Integrator Holding** icon to stop the integrator.
12. At this point you can manipulate various variables within the design and observe the response of other variable

To view a legend for the Strip Chart variables, right-click inside the Strip Chart view and select **Legend** from the menu.

You can also maximize the Strip Chart views to see the details.



# B HYSYS Applications

This section contains examples that illustrate many of the features of HYSYS. The applications include aspects of Conceptual Design, Steady State modeling and Optimization. All aspects are not illustrated in every example, so the areas of interest in each application are highlighted below.

The HYSYS Applications describe, in general terms, how to completely model particular processes using various features of HYSYS—detailed methods of constructing the models are not provided. If you require detailed descriptions on how to construct models in HYSYS, see the comprehensive Tutorial section of this manual.

The examples in the Applications section provide a broad range of problems related to various segments of industry and are organized as follows.

## Gas Processing

### G1 Acid Gas Sweetening with DEA — Steady State Modeling, Optional Amines Package

The Amines Property Package is an optional property package. It is not included in the base version of HYSYS. Contact your Hyprotech agent for more information, or e-mail us at [info@hyprotech.com](mailto:info@hyprotech.com).

A sour natural gas stream is stripped of H<sub>2</sub>S and CO<sub>2</sub> in a Contactor (absorber) tower. The rich DEA (diethanolamine) is regenerated in a Stripping tower and the lean DEA is recycled back to the Contactor. To solve this example, you must have the Amines property package, which is an optional property package. A spreadsheet is used to calculate various loadings and verify that they are within an acceptable range.



## Refining

### R1 Atmospheric Crude Tower — Steady State Modeling, Oil Characterization

A preheated (450°F) light crude (29 API) is processed in an atmospheric fractionation tower to produce naphtha, kerosene, diesel, atmospheric gas oil (AGO) and atmospheric residue products. A complete oil characterization procedure is part of this example application.

### R2 Sour Water Stripper — Steady State Modeling, Sour Thermo Options, Case Study

Sour water is fed to a distillation tower for  $\text{NH}_3$  and  $\text{H}_2\text{S}$  removal. The use of the Sour Peng Robinson (Sour\_PR) is highlighted. HYSYS's built-in Case Study tool is used to examine the effects of varying column feed temperatures.

## Petrochemicals

### P1 Propane/Propylene Splitter — Steady State Modeling, Column Sub-flowsheet

The individual Stripper tower and Rectifier tower components of a propane/propylene splitter system are modeled. Two separate towers in the same Column sub-flowsheet are used in this example to illustrate the simultaneous solution power of HYSYS's Column sub-flowsheet.



## Chemicals

### C1 Ethanol Plant — Steady State Modeling

An ethanol production process is modeled right from the fermentor outlet through to the production of low grade and high grade (azeotropic) ethanol products.

### C2 Synthesis Gas Production — Steady State Modeling, Reaction Manager, Reactors

Synthesis gas ( $\text{H}_2/\text{N}_2$  on a 3:1 basis) is the necessary feedstock for an ammonia plant. The traditional process for creating synthesis gas is explored in this example. Air, steam, and natural gas are fed to a series of reactors, which produces a stoichiometrically correct product. Extensive use of HYSYS's Reaction Manager is illustrated as four individual reactions are grouped into three reaction sets that are used in five different reactors. This example also demonstrates the use of an Adjust operation to control a reactor outlet temperature. The case is then converted to a dynamics simulation by adding valves and assigning pressure flow specifications on the boundary streams. Reactors are sized using the actual gas flow and the residence time. A spreadsheet operation imports the  $\text{H}_2/\text{N}_2$  molar ratio to a ratio controller, controlling the Air flowrate. Temperature controllers are used to achieve the reactors setpoint by manipulating the duty streams.



## HYSYS Extensibility

### XI Case Linking — Steady State Modeling

This case explores the use of the User Unit Operation to link two HYSYS simulation cases such that the changes made to the first case are automatically and transparently propagated to the second case. Within each User Unit Op, two Visual Basic macros are used. The **Initialize()** macro sets the field names for the various stream feed and product connections and created two text user variables. The **Execute()** macro uses the **GetObject** method to open the target link case and then it attempts to locate the material stream, in the target case, named by the **Initialize()** macro.



# G1 Acid Gas Sweetening with DEA

<b>G1.1 Process Description .....</b>	<b>3</b>
<b>G1.2 Setup .....</b>	<b>5</b>
<b>G1.3 Steady State Simulation .....</b>	<b>5</b>
G1.3.1 Installing the DEA CONTACTOR .....	6
G1.3.2 Regenerating the DEA .....	9
<b>G1.4 Simulation Analysis .....</b>	<b>15</b>
<b>G1.5 Calculating Lean &amp; Rich Loadings .....</b>	<b>15</b>
<b>G1.6 Dynamic Simulation .....</b>	<b>17</b>
G1.6.1 Converting from Steady State .....	17
G1.6.2 Adding a Control Scheme .....	27
G1.6.3 Preparing Dynamic Simulation .....	32
<b>G1.7 References .....</b>	<b>34</b>








In this example, a typical acid gas treating facility is simulated. A water-saturated natural gas stream is fed to an amine contactor. For this example, Diethanolamine (DEA) at a strength of 28 wt% in water is used as the absorbing medium. The contactor consists of 20 real stages. The rich amine is flashed from the contactor pressure of 1000 psia to 90 psia to release most of the absorbed hydrocarbon gas before it enters the lean/rich amine exchanger. In the lean/rich exchanger, the rich amine is heated to a regenerator feed temperature of 200°F. The regenerator also consists of 20 real stages. Acid gas is rejected from the regenerator at 120°F, while the lean amine is produced at approximately 255°F. The lean amine is cooled and recycled back to the contactor.

### Figure G1.1





Recommended amine strength ranges:

Lean Amine Strength in Water	
Amine	Wt%
MEA	15-20
DEA	25-35
TEA, MDEA	35-50
DGA	45-65

Figure G1.2





Figure G1.3



There are three basic steps used in modeling this process:

1. **Setup.** The component list includes C1 through C7 as well as N<sub>2</sub>, CO<sub>2</sub>, H<sub>2</sub>S, H<sub>2</sub>O and DEA.
2. **Steady State Simulation.** The case will consist of an absorber scrubbing the inlet gas using a DEA solution, which will be regenerated in a distillation column. Sweet gas will leave the top of the absorber, whereas the rich amine stream from the bottom will be sent to a regenerator column. An analysis on both the **SWEET GAS** and the **ACID GAS** will be performed to satisfy the specified criterion.
3. **Dynamics Simulation.** The steady state solution will be used to size all the unit operations and tray sections. An appropriate control strategy will be implemented and the key variables will be displayed.



## G1.2 Setup

1. Select the following components: **N2, CO2, H2S, C1, C2, C3, i-C4, n-C4, i-C5, n-C5, C6, C7, H2O, and DEAmine.**
2. Select the following property package: **Amines.** The Amines property package is required to run this example problem. This is a D.B. Robinson proprietary property package that predicts the behaviour of amine-hydrocarbon-water systems.
3. Use the Li-Mather/Non-Ideal Thermodynamic model.
4. In the Session Preferences, clone the **Field** unit set, then change the default units for the Liquid Volume Flow to **USGPM** and the molar Flow to **MMSCFD**.

## G1.3 Steady State Simulation

There are two main steps for setting up this case in steady state:

1. **Installing the DEA Contractor.** A 20 stage absorber column will be used to scrub the SOUR GAS stream with DEA solution (DEA TO CONT). The SWEET GAS will leave the tower from the top whereas the pollutant rich liquid will be flashed before entering the REGENERATOR.
2. **Regenerating the DEA.** The liquid stream from the absorber will be regenerated in a 18 tray distillation column with a condenser and reboiler. The ACID GAS will be rejected from the top and the regenerated DEA will be send back to the DEA CONTACTOR.



## G1.3.1 Installing the DEA CONTACTOR

Before the amine contactor can be solved, an estimate of the lean amine feed (DEA TO CONT) and the inlet gas stream (SOUR GAS) must be provided. The DEA TO CONT stream will be updated once the recycle operation is installed and has converged.

DEA to Cont uses Mass fractions; Sour Gas uses Mole fractions.

### Add Feed Streams

Define the following material streams:

DEA TO CONT material stream	
In this cell...	Enter...
Name	DEA TO CONT
Temperature	95 F
Pressure	995 psia
Std Ideal Liq Vol Flow	190 USGPM
CO2 Mass Frac.	0.0018
Water Mass Frac.	0.7187
DEA Mass Frac.	0.2795
SOUR GAS material stream	
In this cell...	Enter...
Name	SOUR GAS
Temperature	86.0000 F
Pressure	1000.0000 psia
Molar Flow	25 MMSCFD
N2 Mole Frac.	0.0016
CO2 Mole Frac.	0.0413
H2S Mole Frac.	0.0172
C1 Mole Frac.	0.8692
C2 Mole Frac.	0.0393
C3 Mole Frac.	0.0093
iC4 Mole Frac.	0.0026
nC4 Mole Frac.	0.0029
iC5 Mole Frac.	0.0014
nC5 Mole Frac.	0.0012
nC6 Mole Frac.	0.0018
nC7 Mole Frac.	0.0072
H2O Mole Frac.	0.005
DEA Mole Frac.	0.000



## Add a Separator

Any free water carried with the gas is first removed in a separator operation (V-100). Add and define the following separator operation:

Separator [V-100]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlets	SOUR GAS
	Vapour Outlet	GAS TO CONTACTOR
	Liquid Outlet	FWKO
Design [Parameters]	Pressure drop	0 psi

## Add an Absorber Column

- Before installing the column, select **Preferences** from the **Tools** menu. On the **Simulation** tab, ensure that the **Use Input Experts** checkbox is checked, then close the view. The contactor can now be installed.
- Install an Absorber column operation with the specifications shown below.

The Amines property package requires that real trays be modeled in the contactor and regenerator operations, but in order to simulate this, component specific efficiencies are required for H<sub>2</sub>S and CO<sub>2</sub> on a tray by tray basis. These proprietary efficiency calculations are provided in the column as part of the Amines package. Tray dimensions must be supplied to enable this feature.


Absorber Column [DEA CONTACTOR]		
Page	In this cell...	Enter...
Connections	No. of Stages	20
	Top Stage Inlet	DEA TO CONT
	Bottom Stage Inlet	GAS TO CONTACTOR
	Ovhd Vapour Outlet	SWEET GAS
	Bottoms Liquid Outlet	RICH DEA
Pressure Profile	Top	995 psia
	Bottom	1000 psia
Temperature Estimates	Top Temperature	100 F
	Bottom Temperature	160 F



Using this information, the component specific tray efficiencies can be calculated.

3. Run the Column.
4. Once it has converged, click the **Parameters** tab and select the **Efficiencies** page.
5. Click the **Component** radio button and note the efficiency values for CO<sub>2</sub> and H<sub>2</sub>S on each tray. HYSYS provides an estimate of the component tray efficiencies but allows you to specify the individual efficiencies if required.

Figure G1.4



Next, add a valve and another separator. The stream Rich DEA from the absorber is directed to valve VLV-100, where the pressure is reduced to 90 psia; close to the regenerator operating pressure.



## Add a Valve

Valve [VLV-100]		
Tab [Page]	In the cell...	Enter...
Design [Connections]	Inlet	RICH DEA
	Outlet	DEA TO FLASH TK
Worksheet [Conditions]	Pressure (DEA TO FLASH TK)	90 psia

## Add a Separator

Gases that are flashed off from the RICH DEA stream are removed using the rich amine flash tank (FLASH TK) which is modeled using a Separator operation.

Separator [FLASH TK]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	DEA TO FLASH TK
	Vapour Outlet	FLASH VAP
	Liquid Outlet	RICH TO L/R

## G1.3.2 Regenerating the DEA

### Add a Heat Exchanger

The stream RICH TO L/R is heated to 200°F (REGEN FEED) in the lean/rich exchanger (E-100) prior to entering the regenerator, which is represented by a distillation column. Heat is supplied to release the acid gas components from the amine solution, thereby permitting the DEA to be recycled back to the contactor for reuse.



The heat exchanger is defined below.

Heat Exchanger [E-100]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Tube Side Inlet	RICH TO L/R
	Tube Side Outlet	REGEN FEED
	Shell Side Inlet	REGEN BTTMS
	Shell Side Outlet	LEAN FROM L/R
Design [Parameters]	Tubeside Delta P	10 psi
	Shellside Delta P	10 psi
Rating [Sizing]	Tube Passes per Shell	1
Worksheet [Conditions]	Temperature (REGEN FEED)	200 F

## Add a Distillation Column

1. Add a distillation column, configured as shown in the following table. The amine regenerator is modeled as a distillation column with 20 real stages - 18 stages in the Tray Section plus a Reboiler and Condenser.

Distillation Column [Regenerator]		
Page	In this cell...	Enter...
Connections	No. of Stages	18
	Inlet Streams (Stage)	REGEN FEED (4)
	Condenser Type	Full Reflux
	Ovhd Vapour	ACID GAS
	Bottoms Liquid	REGEN BTTMS
	Reboiler Energy Stream	RBLR Q
	Condenser Energy Stream	COND Q
Pressure Profile	Condenser Pressure	27.5 psia
	Cond Pressure Drop	2.5 psi
	Reboiler Pres.	31.5 psia



For this tower, the component efficiencies will be fixed at 0.80 for H<sub>2</sub>S and 0.15 for CO<sub>2</sub>. The efficiencies of the condenser and reboiler must remain at 1.0, so enter the efficiencies for stages 1-18 only.

2. Select the **Component** radio button in the Efficiency Type group (**Parameters** tab, **Efficiencies** page), then click the **Reset H<sub>2</sub>S CO<sub>2</sub>** button.
3. Type the new efficiencies into the matrix.
4. Specify a **Damping Factor** of **0.40** (**Parameters** tab, **Solver** page) to provide a faster, more stable convergence.

Distillation Column [Regenerator]		
Tab [Page]	In this cell...	Enter...
<b>Parameters [Efficiencies]</b>	Condenser	1.0
	Reboiler	1.0
	1_TS to 18_TS CO <sub>2</sub>	0.15
	1_TS to 18_TS H <sub>2</sub> S	0.80
<b>Parameters [Solver]</b>	Damping Factor	0.40

5. Add two new column specifications called **Reboiler Duty** and **T Top** (**Design** tab, **Specs** page).
6. Set the default specifications as shown below.
7. Delete the **Reflux Rate** and **REGEN Bttms Rate** specifications from the Column Specification list in the Column property view.

Regenerator Specifications		
Tab [Page]	In this cell...	Enter...
<b>Design [Specs]</b>	Name	T Top
	Stage	Condenser
	Spec Value	179.6 F
	Name	Reboiler Duty
	Energy Stream	RBLR Q@COL2
	Spec Value	1.356e7 BTU/hr
	Name	Reflux Ratio
	Stage	Condenser
	Flow Basis	Molar
	Spec Value	0.5
	Name	Ovhd Vap Rate
	Draw	ACID GAS@COL2
	Flow Basis	Molar
	Spec Value	2.0 MMSCFD



8. Set the **T Top** and **Reboiler Duty** specifications to Active; the Reflux Ratio and Ovhd Vap Rate specifications should be set as Estimates only.

The reboiler duty is based on the guidelines provided below, which should provide an acceptable H<sub>2</sub>S and CO<sub>2</sub> loading in the lean amine.

Recommended Steam Rates lb Steam / USGAL Lean Amine (based on 1000 BTU / lb Steam)	
Primary Amine (e.g., MEA)	0.80
Secondary Amine (e.g., DEA)	1.00
Tertiary Amine (e.g., MDEA)	1.20
DGA	1.30

Water make-up is necessary, since water will be lost in the absorber and regenerator overhead streams.

9. Install a Mixer operation to combine the lean amine from the regenerator with the MAKEUP H<sub>2</sub>O stream. These streams mix at the same pressure.
10. Define the composition of MAKEUP H<sub>2</sub>O as all water, and specify a temperature of 70°F and pressure of 21.5 psia. The flow rate of the total lean amine stream will be defined at the outlet of the mixer, and HYSYS will calculate the required flow of makeup water.
11. Set the overall circulation rate of the amine solution by specifying a Standard Ideal Liquid Volume Flow of 190 USGPM in stream DEA TO COOL. HYSYS will back-calculate the flow rate of makeup water required.

Mixer [MIX-100]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlets	MAKEUP H <sub>2</sub> O
		LEAN FROM L/R
	Outlet	DEA TO COOL
Design [Parameters]	Automatic Pressure Assignment	Set Outlet to Lowest Inlet
Worksheet [Conditions]	Temperature (MAKEUP H <sub>2</sub> O)	70 F
	Pressure (MAKEUP H <sub>2</sub> O)	21.5 psia
	Std Liq Vol Flow (DEA to Cool)	190.5 USGPM
Worksheet [Composition]	H <sub>2</sub> O Mass Frac. (MAKEUP H <sub>2</sub> O)	1.0



When you have finished specifying the DEA TO COOL stream you will receive a warning message stating that the temperature of the Makeup H<sub>2</sub>O stream exceeds the range of the property package and the stream will turn yellow. Since there is no DEA present in this stream, the warning can be ignored without negatively affecting the results of this case.

## Add a Cooler

Add a cooler and define it as indicated below. Cooler E-101 cools the lean DEA on its way to the main pump.

Cooler [E-101]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	DEA TO COOL
	Outlet	DEA TO PUMP
	Energy Stream	COOLER Q
Design [Parameters]	Delta P	5 psi

## Add a Pump

The Cooler and the Pump operations will remain unconverged until the Set operation has been installed.

Add a pump and define it as indicated below. Pump P-100 transfers the regenerated DEA to the Contactor.

Pump [P-100]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	DEA TO PUMP
	Outlet	DEA TO RECY
	Energy	PUMP Q
Worksheet [Conditions]	Temperature [F] (DEA TO RECY)	95°F



The Cooler and the Pump operations will remain unconverged until the Set operation has been installed.

## Add a Set Operation

Install a Set operation (SET-1) to maintain the pressure of stream DEA TO RECY at 5 psi lower than the pressure of the gas feed to the absorber.

Set [SET-1]		
Tab [Page]	In this cell...	Enter...
Connections	Target	DEA TO RECY
	Target Variable	Pressure
	Source	GAS TO CONTACTOR
Parameters	Multiplier	1
	Offset	-5

## Add a Recycle Operation

A Recycle operation is installed with the fully defined stream DEA TO RECY as the inlet and DEA TO CONT as the outlet. The lean amine stream, which was originally estimated, will be replaced with the new, calculated lean amine stream and the contactor and regenerator will be run until the recycle loop converges.

To ensure an accurate solution, reduce the sensitivities for flow and composition as indicated below.

Recycle [RCY-1]		
Tab [Page]	In this cell...	Enter...
Connections	Inlet	DEA TO RECY
	Outlet	DEA TO CONT
Parameters [Tolerance]	Flow	1.0
	Composition	0.1



## G1.4 Simulation Analysis


The incoming sour gas contains 4.1% CO<sub>2</sub> and 1.7% H<sub>2</sub>S. For an inlet gas flow rate of 25 MMSCFD, a circulating solution of approximately 28 wt.% DEA in water removes virtually all of the H<sub>2</sub>S and most of the CO<sub>2</sub>. A typical pipeline specification for the sweet gas is no more than 2.0 vol.% CO<sub>2</sub> and 4 ppm (volume) H<sub>2</sub>S. If you look at the property view of the Sweet Gas stream you will see the sweet gas produced easily meets these criteria.

## G1.5 Calculating Lean & Rich Loadings

Concentrations of acid gas components in an amine stream are typically expressed in terms of amine loading—defined as moles of the particular acid gas divided by moles of the circulating amine. The Spreadsheet in HYSYS is well-suited for this calculation. Not only can the loading be directly calculated and displayed, but it can be incorporated into the simulation to provide a “control point” for optimizing the amine simulation. Also for convenience, the CO<sub>2</sub> and H<sub>2</sub>S volume compositions for the Sweet Gas stream are calculated.

The following variables are used for the loading calculations.

**Figure G1.5**





The following formulas will produce the desired calculations.

Figure G1.6





Figure G1.7



The acid gas loadings can be compared to values recommended by D.B. Robinson as shown below.

**Maximum Acid Gas Loadings (moles acid gas/mole of amine)**

	CO2	H2S
MEA, DGA	0.5	0.35
DEA	0.45	0.30
TEA, MDEA	0.30	0.20



## G1.6 Dynamic Simulation

In the second part of the application, the steady state case will be converted into dynamics. The general steps that will be used to navigate through this detailed procedure are as follows:

1. **Converting from Steady State.** To prepare the case for dynamic simulation, valves will be installed to define pressure flow relations and PF specifications will be added to selected streams. The tray sizing utility will be implemented for sizing tray sections; all other unit operations will be sized.
2. **Adding Controllers.** In this step, appropriate controllers will be installed and defined manually.
3. **Preparing the Dynamics Simulation.** In the last step, the Databook will be set up. Changes will be made to key variables in the process and the dynamic behaviour of the model will be observed.

### G1.6.1 Converting from Steady State



Break Connection icon

Use the **Break Connection** icon to break the connection between streams and unit operations.



Attach Mode icon

Use the **Attach Mode** icon to reconnect them.

### Changing the PFD

A few changes will have to be made to the PFD in order to operate in Dynamic mode.

1. Delete the **Set-1** unit operation.
2. Set the pressure of the DEA TO RECY stream to **995 psia**.
3. Install a Recycle operation between the REGEN BTTMS stream and the E-100 exchanger.

**The Recycle operation only functions in Steady State mode. Its sole purpose in this case is to provide a suitable solution before entering Dynamic mode.**

Recycle	RCY-2	
Page	In this cell...	Enter...
Connections	Inlet	REGEN BTTMS
	Outlet	REGEN BTTMS-1



4. Delete the Std. Ideal Liq Vol Flow value in stream DEA TO COOL.
5. Specify the Std. Ideal Liq. Vol. Flow in stream MAKEUP H2O at 2.195 USGPM.
6. Delete MIX-100 and replace it with a tank, V-101. Name the vapour outlet from the tank Nitrogen Blanket.
7. Change the Heat Exchanger model of the E-100 exchanger from Exchanger Design (End Point) to Dynamic Rating. Delete the temperature of the REGEN FEED stream, since it will be calculated by the exchanger. Use the following table to set the new specifications for the exchanger.

Heat Exchanger	E-100	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Shell Side Inlet	REGEN BTTMS TO L/R
Design [Parameters]	Heat Exchanger Model	Dynamic Rating
Rating [Parameters]	Model	Basic
	Overall UA	100270 Btu/F-hr
	Shell Side Delta P	134 psi
	Tube Side Delta P	55.6 psi

## Add Pumps

Add the following pumps to define the pressure flow relation.

Two pumps are added because Dynamics mode performs rating calculations that consider pressure differences and flow resistance. To accommodate this, you add equipment that significantly impacts the pressure and drives flow.

Pump Name	P-101	
Tab [Page]	In this cell...	Enter...
Design [Connection]	Inlet	RICH TO PUMP
	Outlet	RICH TO VALVE
	Energy	Q-100
Design [Parameters]	Duty	3739.72 Btu/hr
Comments	Add this pump between the separator FLASH TK and the stream RICH to L/R.	
	<b>P-102</b>	
Tab [Page]	In this cell...	Enter...
Design [Connection]	Inlet	REGEN BTTMS
	Outlet	REGEN BTTMS TO VALVE
	Energy	Q-101
Design [Parameters]	Power	1.972e5 Btu/hr
Comments	Add this pump between the stream REGEN BTTMS and the recycle RCY-2.	



## Add Valves

Add the following valves to define the pressure flow relation.

Valve Name	VLV-FWKO	
Tab [Page]	In this cell...	Enter...
Design [Connection]	Inlet	FWKO
	Outlet	FWKO-1
Worksheet [Conditions]	Pressure (FWKO-1)	986.5 psia
Rating [Sizing]	Valve Opening	50%
	VLV-Flash Vap	
Tab [Page]	In this cell...	Enter...
Design [Connection]	Inlet	FLASH VAP
	Outlet	FLASH VAP-1
Worksheet [Conditions]	Pressure (Flash Vap-1)	89.99 psia
Rating [Sizing]	Valve Opening	50%
	VLV-101	
Tab [Page]	In this cell...	Enter...
Design [Connection]	Inlet	RICH TO VALVE
	Outlet	RICH TO L/R
Design [Parameters]	Delta P	5.8 psi
Rating [Sizing]	Valve Opening	50%
Comments	Add this valve between the pump P-101 and the stream RICH TO L/R.	
	VLV-102	
Tab [Page]	In this cell...	Enter...
Design [Connection]	Inlet	REGEN BTTMS TO VALVE
	Outlet	REGEN BTTMS-2
Design [Parameters]	Delta P	13.53 psi
Rating [Sizing]	Valve Opening	50%
Comments	Add this valve between the stream REGEN BTTMS TO VALVE and the recycle RCY-2.	



Valve Name	VLV-103	
Tab [Page]	In this cell...	Enter...
Design [Connection]	Feed	DEA TO VALVE
	Product	DEA TO COOL
Design [Parameters]	Delta P	1 psi
Rating [Sizing]	Valve Opening	50%
Comments	Add this valve between MIX-100 and the stream DEA TO COOL.	
	VLV-100@COL1	
Tab [Page]	In this cell...	Enter...
Design [Connection]	Feed	1@COL1
	Product	SWEET GAS@COL1
Design [Parameters]	Delta P	1 psi
Rating [Sizing]	Valve Opening	50%
Comments	Add this valve between the vapour outlet of the absorber DEA Contactor and the stream SWEET GAS in the absorber sub-flowsheet.	
	VLV-100@COL2	
Tab [Page]	In this cell...	Enter...
Design [Connection]	Feed	2@COL2
	Product	ACID GAS@COL2
Design [Parameters]	Delta P	1 psi
Rating [Sizing]	Valve Opening	50%
Comments	Add this valve between the vapour outlet of the distillation column REGENERATOR and the stream ACID GAS in the Regenerator Column sub-flowsheet.	

Before proceeding any further, ensure that the case is completely solved.

1. Open the valves property view and move to the **Sizing** page of the **Rating** tab.
2. Select the **User Input** radio button and specify the Valve Opening as indicated.
3. Click the **Size Valve** button.
4. Repeat for all valves in the simulation.



## Adding Pressure Flow Specifications

For more information regarding Pressure-Flow specifications in Column unit operations see [Chapter 8 - Column](#) in the **Operations Guide**.

The pressure-flow specification must be activated in the Dynamics tab on the Specs page by selecting the Active checkbox. The steady state pressure-flow values should be used as a specification.

In order to run the integrator successfully, the degrees of freedom for the flowsheet must be reduced to zero by setting the pressure-flow specifications. Normally, you would make one pressure-flow specification per flowsheet boundary stream, however, there are exceptions to the rule.

One extra pressure flow specification is required for the condenser attached to the column Regenerator. This rule applies only if there are no pieces of equipment attached to the reflux stream downstream of the condenser. Without other pieces of the equipment (i.e., pumps, coolers, valves) to define the pressure flow relation of these streams, they must be specified with a flow specification.

1. In the Main flowsheet, add the following pressure-flow specifications to the boundary streams.

Material Stream	Pressure Specification	Flow Specification	Value
<b>SOUR GAS</b>	Inactive	Molar Flow	25 MMSCFD
<b>FWKO-1</b>	Active	Inactive	986.5 psia
<b>FLASH VAP-1</b>	Active	Inactive	89.99 psia
<b>MAKEUP H2O</b>	Inactive	Ideal Liq Vol Flow	2.195 USGPM
<b>SWEET GAS</b>	Active	Inactive	994 psia
<b>ACID GAS</b>	Active	Inactive	26.5 psia
<b>REFLUX@COL2</b>	Inactive	Mass Flow	2983 lb/hr
<b>Nitrogen Blanket</b>	Active	Inactive	21.5 psia

2. Ensure the **PF Relation** checkbox for all the valves is checked (**Dynamics** tab, **Specs** page).
3. Activate the **Efficiency** and **Power** checkboxes for pumps (you may have to deactivate the **Pressure Rise** checkbox).
4. On the E-100 property view, click the **Calculate K's** button (**Dynamics** tab, **Specs** page).
5. Also on the cooler E-101 property view, set the pressure flow option instead of the pressure drop by selecting the **Overall k Value** checkbox and deactivating the pressure drop checkbox.
6. Deactivate the **Delta P** checkbox and select the **k** checkbox for both the Shell and Tube side.



## Equipment Sizing

In preparation for dynamic operation, both column tray sections and the surrounding equipment must be sized. In steady state simulation, the column pressure drop is user specified. In dynamics, it is calculated using dynamic hydraulic calculations. Complications will arise in the transition from steady state to dynamics if the steady state pressure profile across the column is very different from that calculated by the Dynamic Pressure-Flow solver.

### Column Tray Sizing

1. From the **Tools** menu, select **Utilities**. Add a Tray Sizing utility to size the DEA Contactor tray section.
2. Click the **Select TS** button. The Select Tray Section view appears.
3. From the Flowsheet list, select DEA Contactor. From the Object list, select TS-1.
4. Click the Auto section button to calculate the tray section dimension. Accept all the defaults.
5. Select the **Trayed** radio button in the Section Results group (**Performance** tab, **Results** page).
6. Confirm the following tray section parameters for Section\_1.

Variable	Value
Section Diameter	3.5 ft
Weir Height	2 in
Tray Spacing	24 in
Weir Length	34.81 in

7. Select the **Trayed** radio button in the Section Results group. The number of flow paths for the vapour is 1.
8. Calculate the Actual Weir Length using the Weir Length divided by the number of flow paths for the vapour.

Variable	Value
Actual Weir Length (Weir Length/1)	34.81 in

9. Open the DEA Contactor column property view.
10. Click the **Rating** tab, then select the **Tray Sections** page.



11. Enter the tray section parameters for TS-1 obtained from the tray sizing utility.
12. Size the Regenerator tray section following the same procedure described above for the DEA Contactor. The Auto Section function may create two tray sections; ensure that the column is sized with only one tray section for all trays. Delete the section that does not match the specifications below.
13. Confirm the following tray section parameters for Main TS in the Regenerator:

Variable	Value
Section Diameter	3.5 ft
Weir Height	2 in
Tray Spacing	24 in
Total Weir Length	33.75 in
Number of Flow Paths	1
Actual Weir Length	33.75 in

14. In the Regenerator column property view, click the **Rating** tab, then select the **Tray Sections** page.
15. Enter the Section Diameter value shown above.

## Vessel Sizing

The Condenser and Reboiler operations in the Regenerator column sub-flowsheet require proper sizing before they can operate effectively in Dynamics mode. The volumes of these vessel operations are determined using a 10 minute liquid residence time.

1. Open the Regenerator property view, then enter the Column Environment.
2. Open the Condenser property view.
3. Click the **Worksheet** tab, then select the **Conditions** page.
4. Confirm the following Std Ideal Liquid Volumetric Flow.

Stream	Std Ideal Liquid Volume Flow
Reflux	5.975 USGPM



- Calculate the vessel volume as follows, assuming a 50% liquid level residence volume.

$$Vessel\ Volume = \frac{Total\ Liquid\ Exit\ Flow \cdot Residence\ Time}{0.5} \quad (G1.1)$$

- Click the **Dynamics** tab, then select the **Specs** page.
- In the Model Details group, specify the vessel volume as 15.97 ft<sup>3</sup> (as calculated with the above formula).
- Specify the Level Calculator as a Horizontal cylinder.
- Open the Reboiler property view.
- Click the **Worksheet** tab, then select the **Conditions** page. Confirm the following Std Ideal Liquid Volume Flow.

Stream	Std Ideal Liquid Volume Flow
To Reboiler	239.7 bbl/day

- Calculate the vessel volume using Equation (G1.1) and assuming a 50% liquid level residence time.
- Click the **Dynamics** tab, then select the **Specs** page.
- In the Model Details group, specify the vessel volume as 641 ft<sup>3</sup> and the Level Calculator as a Horizontal cylinder.

## Separator Sizing

- Use a residence time of 5 min and a 50% liquid level to size the separator FLASH TK.
- Confirm the Std Ideal Liquid Volume flow in the table below and enter the vessel volume.



3. Click the **Rating** tab, then select the **Sizing** page. Select the Vertical orientation radio button for the separator.

Separator Name	FLASH TK	
Tab [Page]	In this cell...	Enter...
Worksheet [Conditions]	Std Liq Vol Flow (RICH TO L/R)	498.27 USGPM
Rating [Sizing]	Volume	660 ft <sup>3</sup>
	<b>V-100</b>	
Tab [Page]	In this cell...	Enter...
Rating [Sizing]	Diameter	5.94 ft
	Length	29.7 ft

The vapour flow rate through V-100 is large as compared to the liquid flow rate, therefore Separator V-100 is sized according to the terminal vapour velocity (Vertical Cylinder).

## Tank Sizing

The tank V-101 will be sized with a 10 minute liquid residence time and a 75% liquid level. Confirm the volumetric flow rate of the exit stream and specify the vessel volume (**Rating** tab, **Sizing** page).

Tank	V-101	
Tab [Page]	In this cell...	Enter...
Worksheet [Conditions]	LiqVol Flow (DEA TO VALVE)	194.4 USGPM
Rating [Sizing]	Volume	346.4 ft <sup>3</sup>
Design [Parameters]	Liquid Level	75%

## Heat Exchanger Sizing

The Shell and Tube heat exchanger E-100 will be sized with a 10 minute residence time for both the shell and the tube side (enter respective sizes on the **Rating** tab, **Parameters** page).

Heat Exchanger	E-100	
Tube Side Sizing		
Worksheet [Conditions]	Std Ideal Liq Vol Flow (RICH TO L/R)	498.27 USGPM
Rating [Sizing]	Volume	666 ft³



Heat Exchanger	E-100	
Shell Side Sizing		
Worksheet [Conditions]	Std Ideal Liq Vol Flow (REGEN BTTMS TO L/R)	691.3 USGPM
Rating [Sizing]	Volume	925.2 ft³

A 10 minute liquid residence time will also be used for sizing the cooler E-101 (Dynamics tab, Specs page).

Cooler	E-101	
Tab [Page]	In this cell...	Enter...
Worksheet [Conditions]	Std Ideal Liq Vol Flow (DEA TO COOL)	194.4 USGPM
Dynamics [Specs]	Volume	259.8 ft <sup>3</sup>

## Running the Integrator

1. Switch to the Dynamic mode by clicking the **Dynamic Mode** button. Click **No** when asked if you want the Dynamics Assistant to help you resolve items in Steady State before switching to Dynamic mode.
2. Open the Product Block for stream Nitrogen Flow.
3. Ensure that the radio button for temperature is selected, and the value is specified as **70°F**.
4. Click the **Composition** tab and set the composition to **100% Nitrogen**.
5. Return to the **Conditions** tab, and press the **Export to Stream** button.
6. Open the Integrator view and change the **Step Size** to **0.2** sec on the **General** tab.
7. Click the **Options** tab and make sure that the **Singularity analysis before running** checkbox is selected.
8. Run the integrator for 2 minutes to ensure that the degrees of freedom for pressure flow specification is zero and all the vessels are sized. Select **Non-Equilibrium Vapour** when asked how you want to initialize V-101.



## G1.6.2 Adding a Control Scheme

The following Controllers will be used in the Dynamics model:

- Level
- Temperature
- Pressure
- Flow

### Level Controllers

Level Controller Name	V100-LC	
Tab [Page]	In this cell...	Enter...
Connections	Process Object	V-100
	Process Variable	Liquid Percent Level
	Output Variable	VLV-FWKO
Parameters [Configuration]	PVmin	0%
	PVmax	100%
	Action	Direct
	Mode	Auto
	SP	50%
	Kc	2
	Ti	2
FLASH TK-LC		
Tab [Page]	In this cell...	Enter...
Connections	Process Object	FLASH TK
	Process Variable	Liquid Percent Level
	Output Variable	VLV-101
Parameters [Configuration]	PVmin	0%
	PVmax	100%
	Action	Direct
	Mode	Auto
	SP	50%
	Kc	2
	Ti	2



Level Controller Name		LIC-100
Tab [Page]	In this cell...	Enter...
Connections	Process Object	V-101
	Process Variable	Liquid Percent Level
	Output Variable	MAKEUP H2O
To size the Control Valve for the MAKEUPH2O stream, select the <i>Control Valve</i> button.		
FCV for MAKEUP H2O	Flow Type	Mass Flow
	Min Available	0.0 lb/hr
	Max Available	1200 lb/hr
Parameters [Configuration]	PVmin	0%
	PVmax	100%
	Action	Reverse
	Mode	Auto
	SP	50%
	Kc	2
	Ti	2
		Reb-LC@COL2
Tab [Page]	In this cell...	Enter...
Connections	Process Object	Reboiler@COL2
	Process Variable	Liquid Percent Level
	Output Variable	VLV-102
Parameters [Configuration]	PVmin	0%
	PVmax	100%
	Action	Direct
	Mode	Auto
	SP	50%
	Kc	2
	Ti	2



Level Controller Name		Cond-LC@COL2
Tab [Page]	In this cell...	Enter...
Connections	Process Object	Condenser@ COL2
	Process Variable	Liquid Percent Level
	Output Variable	Reflux
To size the Control Valve for the Reflux stream, select the <i>Control Valve</i> button.		
FCV for Reflux	Flow Type	Mass Flow
	Min Available	0.0 lb/hr
	Max Available	5512 lb/hr
Parameters [Configuration]	PVmin	0%
	PVmax	100%
	Action	Direct
	Mode	Auto
	SP	50%
	Kc	1
	Ti	2



## Temperature Controllers

Temperature Controller Name		TIC-100
Tab [Page]	In this cell...	Enter...
Connections	Process Object	DEA TO PUMP
	Process Variable	Temperature
	Output Variable	COOLER Q
To size the Control Valve for the Cooler Duty stream, select the Control Valve button. To filter high frequency disturbances, click the Parameter tab, select the PV Conditioning page, and change the First Order Time Constant from 15 to 50.		
FCV for COOLER Q	Duty Source	Direct Q
	Min Available	0.0 Btu/hr
	Max Available	2.4e7 Btu/hr
Parameters [Configuration]	PVmin	32 F
	PVmax	122 F
	Action	Direct
	Mode	Auto
	SP	91 F
	Kc	10
	Ti	10
TIC-103@COL2		
Tab [Page]	In this cell...	Enter...
Connections	Process Object	Main TS
	Process Variable	Stage Temperature
	Variable Specifics	18_Main TS
	Output Variable	RBLR Q
To size the Control Valve for the Reboiler Duty stream, select the Control Valve button.		
FCV for RBLR Q	Flow Type	Direct Q
	Min Available	0 Btu/hr
	Max Available	1.9e7 Btu/hr
Parameters [Configuration]	PVmin	176 F
	PVmax	302 F
	Action	Reverse
	Mode	Auto
	SP	255°F
	Kc	2
	Ti	5



## Pressure Controllers

Pressure Controller Name	PIC-100@COL1	
Tab [Page]	In this cell...	Enter...
Connections	Process Object	TS-1@COL1
	Process Variable	Top Stage Pressure
	Output Variable	VLV-100@COL1
Parameters [Configuration]	PVmin	950 psia
	PVmax	1050 psia
	Action	Direct
	Mode	Auto
	SP	995 psia
	Kc	2
	Ti	2
PIC-100@COL2		
Tab [Page]	In this cell...	Enter...
Connections	Process Object	Condenser @COL2
	Process Variable	Vessel Pressure
	Output Variable	VLV-100@COL2
	PVmin	0 psia
	PVmax	50 psia
Parameters [Configuration]	Action	Direct
	Mode	Auto
	SP	31 psia
	Kc	2
	Ti	2



## Flow Controller

Flow Controller Name	RECY-FC	
Tab [Page]	In this cell...	Enter...
Connections	Process Object	DEA TO CONT
	Process Variable	Mass Flow
	Output Variable	VLV-103
Parameters [Configuration]	PVmin	0 lb/hr
	PVmax	220460 lb/hr
	Action	Reverse
	Mode	Auto
	SP	97700 lb/hr
	Kc	0.5
	Ti	0.20

## G1.6.3 Preparing Dynamic Simulation

Now that the case is ready to run in Dynamic mode, the next step is installing a strip chart to monitor the general trends of key variables.

## Monitoring in Dynamics

You may use several variables in the same chart. If you have a large number of variables that you would like to track, use several Strip Charts rather than use all of the variables on one chart. You may use the same variable in more than one Strip Chart.



For this simulation case, use the Databook (CTRL D) to set up two strip charts as defined below.

### StripChart1 - Contactor

Flowsheet	Object	Variable
Case	DEA TO CONT	Mass Flow
Case	GAS TO CONTACTOR	Mass Flow
Case	SWEET GAS	Mass Flow
Case	RICH DEA	Mass Flow
Case	SWEET GAS	Pressure

### StripChart2 - Regenerator

Flowsheet	Object	Variable
Case	REGEN FEED	Mass Flow
Case	ACID GAS	Mass Flow
Case	REGEN BTMMS	Mass Flow
Case	ACID GAS	Pressure

Start the Integrator and allow the variables to line out. If you get an initial numerical error after you start the integrator, start the integrator again. In the Session Preferences view (Simulation tab, Errors group), you can direct these errors to the trace window and have the simulation continue regardless.

After a few minutes the integrator will stop and an error message will appear in the trace window.

1. From the **Simulation** menu, select **Equation Summary View**.
2. Click the **Uncovered** tab and click the **Update Sorted List** button.

The top equation refers to pump P-102. If you examine this pump in the PFD you will see that it is fully on, but its downstream valve has been completely shut by a controller. As an advanced exercise, you can refine the control scheme to address this issue.




## G1.7 References

Gerunda, Arthur. How to Size Liquid-Vapour Separators Chemical Engineering, Vol. 88, No. 9, McGraw-Hill, New York, (1981).



# R1 Atmospheric Crude Tower



<b>R1.1 Process Description .....</b>	<b>3</b>
<b>R1.2 Setup .....</b>	<b>6</b>
R1.2.1 Components & Fluid Package .....	6
R1.2.2 Oil Characterization .....	6
<b>R1.3 Steady State Simulation .....</b>	<b>10</b>
R1.3.1 Simulate the Pre-Fractionation Train .....	10
R1.3.2 Install Atmospheric Crude Fractionator .....	12
<b>R1.4 Results .....</b>	<b>18</b>








# R1.1 Process Description

Figure R1.1




After passing through a preheat train, 100,000 barrel/day of 29.32° API crude is fed into a pre-flash separator operating at 450° F and 75 psia. The vapour from this separator bypasses the crude furnace and is re-mixed with the hot (650° F) pre-flash liquids leaving the furnace. The combined stream is then fed to the atmospheric crude column.



The column operates with a total condenser, three coupled side strippers, and three pump around circuits.

Figure R1.2



A naphtha product is produced overhead, a kerosene product is produced from the first side stripper, a diesel product is produced from the second side stripper, and an atmospheric gas oil (AGO) is produced from the third side stripper. Both the AGO side stripper and the diesel side stripper are 'steam stripped', while the kerosene side stripper has a reboiler.



The following Assay data is used to characterize the oil for this example:

Assay Liq Volume %	Boiling Temperature (°F)
0.0	15.0
4.5	90.0
9.0	165.0
14.5	240.0
20.0	310.0
30.0	435.0
40.0	524.0
50.0	620.0
60.0	740.0
70.0	885.0
76.0	969.0
80.0	1015.0
85.0	1050.0

Light Ends	Liq Volume %
Methane	0.0065
Ethane	0.0225
Propane	0.3200
i-Butane	0.2400
n-Butane	0.8200
H2O	0.0000

Bulk Properties	
Standard Density	29.32° API

Any other library components required for the overall simulation (e.g., H<sub>2</sub>O) should be selected as well.

There are two basic steps in this process simulation:

1. **Setup.** The component list must include C1 to C4 light ends components as well as the hypocomponents that will be used to represent the C5+ portion of the crude oil. The Oil Characterization procedure in HYSYS will be used to convert the laboratory data into petroleum hypocomponents.
2. **Steady State Simulation.** This case will be modeled using a Pre-Fractionation Train consisting of a Separator and Heater. The Outlet stream will then fed to an Atmospheric Crude Fractionator. The results will be displayed. **Dynamic Simulation** - The steady state solution will be used to size all the unit operations and tray section. An appropriate control strategy will be implemented and the key variables will be displayed on a strip chart.



## R1.2 Setup

From the Tools menu, select Preferences, and set the unit set to Field units (Variables tab, Units page). Next, you will establish the property package and Component Basis that will be used in the simulation.

### R1.2.1 Components & Fluid Package

This example will be developed using Field units.

1. Define a fluid package with Peng-Robinson as the Property Package.
2. Create a components list that contains the following: methane, ethane, propane, i-butane, n-butane and water as components.

### R1.2.2 Oil Characterization



Oil Environment icon

Click the **Oil Environment** icon to enter the Oil Characterization Environment, using the fluid package you just created. Three steps are required for characterizing the oil:

1. Define the Assay.
2. Create the Blend.
3. Install Oil in the Flowsheet.



## Define the Assay

1. On the Assay page of the Oil Characterization view, click the **Add** button. This will create a new assay, and you will see the Assay view.
2. Change the **Bulk Properties** setting to **Used**.
3. Complete the Input data for the Bulk Properties as shown below:

Figure R1.3

Input Data	
Molecular Weight	<empty>
Standard Density	54.82 lb/ft3
Watson UGPK	<empty>
Viscosity Type	Dynamic
Viscosity 1 Temp	100.0 F
Viscosity 1	<empty>
Viscosity 2 Temp	210.0 F
Viscosity 2	<empty>

4. Since the TBP data is supplied, select **TBP** from the Assay Data Type drop-down list.
5. Select **Liquid Volume%** from the Assay Basis drop-down list.
6. Click the **Edit Assay** button and enter the data as follows.

Figure R1.4

Assay Input Data	
Assay Percent (%)	Temperature (F)
0.0000	15.00
4.500	90.00
9.000	165.0
14.50	240.0
20.00	310.0
30.00	435.0
40.00	524.0
50.00	620.0
60.00	740.0
70.00	885.0
76.00	969.0
80.00	1015
85.00	1050
<empty>	<empty>

All input curves except distillation are on midpoint basis. Dependent curves will be shifted to middle.

Cancel OK

7. In the Assay Definition group, click the Light Ends drop-down list and select **Input Composition**.
8. In the Input Data group, click the **Light Ends** radio button.



9. Enter the light ends data as follows.

Figure R1.5

Input Data

☐ Bulk Props  
☒ Light Ends  
☐ Distillation

Light Ends Basis: **Liquid Volume %**

Light Ends	Composition	NBP [F]
Methane	6.500e-003	-258.7
Ethane	2.250e-002	-127.5
Propane	0.3200	-43.78
i-Butane	0.2400	10.89
n-Butane	0.8200	31.10
H2O	0.0000	212.0

Percent of Light Ends in Assay: **1.4090**

You can scroll through this table to view all 50 points of the Working Curve.

10. Upon completion of characterizing the assay, select the **Calculate** button. HYSYS will calculate the Working Curves, which can be viewed on the Working Curve tab.

Figure R1.6

Assay: Assay-1

Assay Working Curves

Point #	Moles	Cum. Moles	NBP [F]	Mole Wt	Mass Density [lb/ft3]	Viscosity 1 [cP]	Viscosity 2 [cP]
0	0.00000	0.00000	31.10	56.89	36.49	0.143	0.083
1	0.01000	0.01000	48.77	59.71	43.04	0.262	0.136
2	0.01000	0.02000	64.86	62.74	43.50	0.280	0.147
3	0.01000	0.03000	81.66	65.92	43.96	0.299	0.159
4	0.01000	0.04000	98.48	69.54	44.41	0.310	0.168
5	0.01000	0.05000	115.2	73.45	44.85	0.316	0.174
6	0.01000	0.06000	131.8	77.38	45.28	0.305	0.174
7	0.01000	0.07000	148.1	81.33	45.69	0.307	0.187
8	0.01000	0.08000	164.0	85.15	46.08	0.327	0.197
9	0.01000	0.09000	177.5	87.99	46.41	0.345	0.207
10	0.01000	0.10000	187.4	90.37	46.65	0.360	0.215
11	0.02500	0.12500	214.9	98.77	47.30	0.408	0.239
12	0.02500	0.15000	247.6	108.1	48.06	0.477	0.273
13	0.02500	0.17500	278.9	117.4	48.75	0.556	0.310
14	0.02500	0.20000	310.2	127.2	49.43	0.650	0.353

11. Close the Assay view.



## Create the Blend (Cut the Oil)

Compositions	
	Blend-1
Methane	0.0003
Ethane	0.0006
Propane	0.0088
i-Butane	0.0055
n-Butane	0.0196
H2O	0.0000
NBP_54	0.0403
NBP_86	0.0487
NBP_123	0.0485
NBP_161	0.0502
NBP_192	0.0519
NBP_233	0.0504
NBP_269	0.0490
NBP_306	0.0453
NBP_343	0.0417
NBP_379	0.0394
NBP_416	0.0396
NBP_453	0.0444
NBP_489	0.0457
NBP_525	0.0415
NBP_562	0.0359
NBP_599	0.0313
NBP_635	0.0267
NBP_672	0.0233
NBP_709	0.0207
NBP_745	0.0181
NBP_782	0.0162
NBP_840	0.0314
NBP_921	0.0288

1. Click the **Cut/Blend** tab (Oil Characterization view) and click the **Add** button. The Blend: Blend-1 view appears.
2. Click the **Data** tab, then select the Assay you created in the Available Assays column.
3. Click the **Add** button. HYSYS will transfer that Assay to the Oil Flow Information table.

As a guideline, each Outlet stream from the crude column should contain a minimum of 5 hypocomponents where the composition is greater than 1.0%. Therefore, a total of 30 components should fulfil this requirement.

4. From the Cut Option Selection drop-down list, select **User Points**, then specify the Number of Cuts at 30. HYSYS will calculate the hypocomponents.
5. Click the **Tables** tab to view the hypocomponents.
6. From the Table Type group drop-down list, select **Molar Compositions**.
7. Close the Blend view.

## Install Oil in the Flowsheet

The final step is to install the oil in the flowsheet.

1. Click the **Install Oil** tab of the Oil Characterization view.
2. In the Stream Name cell, type **Raw Crude**. This is the stream name where you would like to “install” the oil.
3. On the Oil Characterization view, click **Return to Basis Environment** button.
4. Click the **Enter Simulation Environment** button on the Simulation Basis Manager view to enter the Main Environment. The Raw Crude stream has been installed.



## R1.3 Steady State Simulation

The following major steps will be taken to set up this case in steady state:

1. **Simulate the Pre-Fractionation Train.** This determines the feed to the atmospheric fractionator, and includes the pre-flash separation, crude furnace and mixer which recombines the pre-flash vapour and furnace outlet stream.
2. **Install the Atmospheric Crude Fractionator.** Add the column steam inlets to the flowsheet and install the crude fractionator using the rigorous distillation column operation.

### R1.3.1 Simulate the Pre-Fractionation Train

#### Inlet Stream

Specify the Inlet stream (Raw Crude) as shown below.

Stream [Raw Crude]	
In this cell...	Enter...
Temperature [F]	450.0°F
Pressure [psia]	75.0 psia
Std Ideal Liq Vol Flow [barrel/day]	100,000 barrel/day

Because the composition has been transferred from the Oil Characterization, the stream is automatically flashed.



## Pre-Flash Operations

Install the Separator, Heater and Mixer and provide the information displayed below:

Separator [PreFlash]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	Raw Crude
	Vapour Outlet	PreFlash Vap
	Liquid Outlet	PreFlash Liq

Heater [Crude Heater]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	PreFlash Liq
	Outlet	Hot Crude
	Energy	Crude Duty
Design [Parameters]	Delta P	10.00 psi
Worksheet [Conditions]	Temperature (Hot Crude)	650 °F

Mixer [Mixer]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlets	Hot Crude PreFlash Vap
	Outlet	Atm Feed


The calculated specifications for the Pre-Fractionation Atm Feed stream appear below.

**Figure R1.7**

Name	Atm Feed
Vapour Fraction	0.6114
Temperature [F]	622.2
Pressure [psia]	65.00
Molar Flow [lbmole/hr]	6227
Mass Flow [lb/hr]	1.282e+006
Liquid Volume Flow [barrel/day]	1.000e+005
Heat Flow [Btu/hr]	-7.464e+008



The Pre-Fractionation train is shown as follows:



## R1.3.2 Install Atmospheric Crude Fractionator

### Steam and Trim Duty Streams

An energy stream can be installed by selecting the appropriate icon from the palette, or a material stream converted to an energy stream on the Util page of the stream property view.

Before simulating the atmospheric crude tower, the steam feeds and the energy stream (Q-Trim - representing the side exchanger on stage 28) to the column must be defined.

The Q-Trim stream does not require any specifications, this will be calculated by the Column.

Three steam streams are fed to various locations in the tower. Specify the steam streams as shown below. Define the composition for each as  $H_2O = 1.0000$ .

These streams could be installed inside the Column Build Environment as well. By taking this approach, you will need to “attach” these streams to the Column Flowsheet so that they can be used in the calculations.

Stream Name	Temperature [F]	Pressure [psia]	Mass Flow [lb/hr]
Main Steam	375.00	150.00	7500.00
Diesel Steam	300.00	50.00	3000.00
AGO Steam	300.00	50.00	2500.00



## Column

Note that Input Experts (Preferences) have been turned Off, and the Column is being configured directly through the Property View.

The main column, Atms Tower, is represented by the following:

- Number of stages is **29** ideal stages (not including the condenser).
- The overhead condenser operates at **19.7** psia and the bottom stage at **32.7** psia.
- The condenser experiences a **9** psi pressure drop.
- The temperature estimates for the condenser, top stage, and bottom stage are **100°F**, **250°F** and **600°F**, respectively.
- Condensed water is removed via a water draw from the three-phase condenser.

HYSYS comes with a 3 Stripper Crude Column template. A Refluxed Absorber template could also be used, but this would add the procedure of installing Side Strippers and Pump Arounds.

For this example, install the **3 Stripper Crude Column** custom template.



Custom Column icon

1. Select the **Custom Column** icon in the Object Palette, then click the **Read an Existing Column Template** button. The Available Column Templates finder view appears.
2. In the **Files of type** drop-down list, select **Column Templates (\*.col)**.
3. From the list, select the **3sscruide.col** template file, then click the **Open** button.

The 3sscruide.col template installed 40 trays, 29 in the Main Tray section, 3 trays in each of the 3 Side Strippers (1 reboiled and 2 steam stripped), a reboiler, and a condenser.



- In the Column Property view, connect the Inlet and Outlet streams to the column sub-flowsheet as shown (Design tab, Connections page).

Figure R1.9

Inlet Streams					
Internal Stream	External Stream	Inlet Stage	Transfer Basis	Split	
Main Steam	Main Steam	29_Main TS	T-P Flash	<input type="checkbox"/>	
Q-Trim	Q-Trim	28_Main TS	None Req'd	<input type="checkbox"/>	
Atm Feed	Atm Feed	28_Main TS	T-P Flash	<input type="checkbox"/>	
Kero_SS_Energy	<< Stream >>	Kero_SS_Reb	None Req'd	<input type="checkbox"/>	
Diesel Steam	Diesel Steam	3_Diesel_SS	T-P Flash	<input type="checkbox"/>	
AGO Steam	AGO Steam	3_AGO_SS	T-P Flash	<input type="checkbox"/>	
Outlet Streams					
Internal Stream	External Stream	Outlet Stage	Type	Transfer Basis	
Residue	Residue	29_Main TS	L	T-P Flash	
Atmos Cond	Atmos Cond	Condenser	Q	None Req'd	
Off Gas	Off Gas	Condenser	V	T-P Flash	
Waste Water	Waste Water	Condenser	W	T-P Flash	
Naphtha	Naphtha	Condenser	L	T-P Flash	
Kerosene	Kerosene	Kero_SS_Reb	L	T-P Flash	
Diesel	Diesel	3_Diesel_SS	L	T-P Flash	
AGO	AGO	3_AGO_SS	L	T-P Flash	
PA_1_Q	<< Stream >>	<empty>	Q	None Req'd	
PA_2_Q	<< Stream >>	<empty>	Q	None Req'd	
PA_3_Q	<< Stream >>	<empty>	Q	None Req'd	
** New **	<< Stream >>				

- Modify the Draw and Return stages of the Pump Arounds and Side Strippers on the corresponding page of the **SideOps** tab.

Figure R1.10

Side Stripper Summary						
	# Stages	Liq Draw Stage	Vap Return Stage	Outlet Flow [lbmole/hr]	Reboiler Duty [Btu/hr]	
Kero_SS	3	9_Main TS	8_Main TS	<empty>	<empty>	
Diesel_SS	3	17_Main TS	16_Main TS	<empty>	<empty>	
AGO_SS	3	22_Main TS	21_Main TS	<empty>	<empty>	

Liquid Pump Around Summary							
	Draw Stage	Return Stage	Flow [lbmole/hr]	Duty [Btu/hr]	Draw T [F]	Return T [F]	Export
PA_1	2_Main TS	1_Main TS	<empty>	<empty>	<empty>	<empty>	<input type="checkbox"/>
PA_2	17_Main TS	16_Main TS	<empty>	<empty>	<empty>	<empty>	<input type="checkbox"/>
PA_3	22_Main TS	21_Main TS	<empty>	<empty>	<empty>	<empty>	<input type="checkbox"/>



Field units are used for column preferences.

- In the Atmos Tower Column view, specify the column information below.

Column [Atms Tower]		
Tab [Page]	In this cell...	Enter...
Parameters [Profiles]	Condenser Pressure	19.7 psia
	1_Main TS Pressure	28.7 psia
	29_Main TS Pressure	32.7 psia
	Condenser Temperature	100°F
	1_Main TS Temperature	250°F
	29_Main TS Temperature	600°F

## Specifications

- On the **Monitor** page of the **Design** tab, input the following values into the default set of specifications supplied with the pre-built 3-Side Stripper Column
  - Change the Pump Around delta T specification to a Duty specification.
  - Change the Basis of each Pump Around Rate specification to Volume Basis before entering the values.
- Delete the Kero SS BoilUp Ratio and the Residue Rate specs (click the **View** button then click **Delete** in the specification property view).
  - Specify the **Reflux Ratio** spec to have a value of 1. Uncheck the Reflux Ratio **Active** checkbox and make it an Estimate only.
  - Change the following default specifications by selecting the specification in the table and clicking the **View** button.

Change the Flow Basis from Molar to Volume before entering values.

Specification	Flow Basis	Spec Type	Spec Value
Kero_SS Prod Flow	Volume		9300 barrel/day
Diesel_SS Prod Flow	Volume		1.925e+04 barrel/day
AGO_SS Prod Flow	Volume		4500 barrel/day
PA_1_Rate(Pa)	Volume		5.000e+04 barrel/day
PA_1_Duty(Pa)		Duty	-5.500e+07 Btu/hr
PA_2_Rate(Pa)	Volume		3.000e+04 barrel/day
PA_2_Duty(Pa)		Duty	-3.500e+07 Btu/hr
PA_3_Rate(Pa)	Volume		3.000e+04 barrel/day
PA_3_Duty(Pa)		Duty	-3.500e+07 Btu/hr
Naptha Prod Rate	Volume		2.300e+04 barrel/day



4. On the **Specs** page of the **Design** tab, add a new specification by clicking the **Add** button in Column Specifications group.
5. Select **Column Liquid Flow** from the list of available specifications. Complete this specification as shown here. This is an Overflash specification for the feed stage.

Figure R1.11

Name	Liquid Flow
Stage	27 Main TS
Flow Basis	Volume
Spec Value	3500.00 barrel/day

Parameters Summary Spec Type

Delete

6. Add a new specification, select **Column Duty** from the list of available specifications.
7. Complete the Kero Reb Duty specification as shown below.

Figure R1.12

Name	Kero Reb Duty
Energy Stream	aro SS Energy @COL1
Spec Value	7.5e+006 Btu/hr

Parameters Summary Spec Type

Delete



8. Add a new specification, select **Column Vapour Flow** specification from the list of available specifications. Complete the Vap Prod Flow specification as shown below.

Figure R1.13

Vap Flow Spec: Vap Prod Flow

Name	Vap Prod Flow
Stage	Condenser
Flow Basis	Molar
Spec Value	0.000000 lbmole/hr

Parameters Summary Spec Type

Delete

The final specification table will appear as shown below:

Figure R1.14

	Specified Value	Current Value	Wt. Error	Active	Estimate	Current
Kero_SS Prod Flow	9300 barrel/day	9.30e+003	-0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Diesel_SS Prod Flow	1.925e+004 barrel/day	1.92e+004	-0.0001	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
AGO_SS Prod Flow	4500 barrel/day	4.50e+003	-0.0002	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_1_Rate(Pa)	5.000e+004 barrel/day	5.00e+004	-0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_1_Duty(Pa)	-5.500e+007 Btu/hr	-5.50e+007	0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_2_Rate(Pa)	3.000e+004 barrel/day	3.00e+004	-0.0001	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_2_Duty(Pa)	-3.500e+007 Btu/hr	-3.50e+007	0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_3_Rate(Pa)	3.000e+004 barrel/day	3.00e+004	-0.0001	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PA_3_Duty(Pa)	-3.500e+007 Btu/hr	-3.50e+007	0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Reflux Ratio	1.000	0.686	-0.3144	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
Naptha Prod Rate	2.300e+004 barrel/day	2.30e+004	-0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Liquid Flow	3500 barrel/day	3.50e+003	-0.0001	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Kero Reb Duty	7.500e+006 Btu/hr	7.50e+006	-0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Vapour Flow	0.0000 lbmole/hr	3.87e-005	-0.0000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

View... Add Spec... Group Active Update Inactive Degrees of Freedom 0

9. Once you have provided all of the specifications, click the **Run** button.



# R1.4 Results

## Workbook Case (Main)

The material stream results for the Workbook Case[Main] appear below.

Figure R1.15

Workbook - Case (Main)							
Name	Raw Crude	PreFlash Vap	PreFlash Liq	Hot Crude	Atm Inlet	AGO Steam	
Vapour Fraction	0.2937	1.0000	0.0000	0.4003	0.6122	1.0000	
Temperature [F]	450.0	450.0	450.0	650.0	622.2	300.0	
Pressure [psia]	75.00	75.00	75.00	65.00	65.00	50.00	
Molar Flow [lbmole/hr]	6214	1825	4389	4389	6214	138.8	
Mass Flow [lb/hr]	1.282e+006	1.602e+005	1.122e+006	1.122e+006	1.282e+006	2500	
Liquid Volume Flow [barrel/day]	1.000e+005	1.490e+004	8.510e+004	8.510e+004	1.000e+005	171.5	
Heat Flow [Btu/hr]	-9.192e+008	-1.004e+008	-8.187e+008	-6.447e+008	-7.452e+008	-1.414e+007	
Name	Main Steam	Diesel Steam	Residue	Off Gas	Waste Water	Naphtha	
Vapour Fraction	1.0000	1.0000	0.0000	1.0000	0.0000	0.0000	
Temperature [F]	375.0	300.0	669.1	107.3	107.3	107.3	
Pressure [psia]	150.0	50.00	32.70	19.70	19.70	19.70	
Molar Flow [lbmole/hr]	416.3	166.5	1397	4.473e+005	700.9	2822	
Mass Flow [lb/hr]	7500	3000	6.216e+005	2.304e+003	1.263e+004	2.474e+005	
Liquid Volume Flow [barrel/day]	514.6	205.8	4.398e+004	2.612e+004	866.4	2.300e+004	
Heat Flow [Btu/hr]	-4.222e+007	-1.697e+007	-3.647e+008	-2.296	-8.561e+007	-2.331e+008	
Name	Kerosene	Diesel	AGO	** New **			
Vapour Fraction	0.0000	0.0000	0.0000				
Temperature [F]	457.5	486.8	571.6				
Pressure [psia]	29.94	30.99	31.70				
Molar Flow [lbmole/hr]	701.9	1114	200.4				
Mass Flow [lb/hr]	1.115e+005	2.429e+005	5.945e+004				
Liquid Volume Flow [barrel/day]	9300	1.925e+004	4500				
Heat Flow [Btu/hr]	-8.098e+007	-1.722e+008	-3.882e+007				

**Material Streams**
Compositions
Energy Streams
Unit Ops

ProductBlock\_Kerosene  
Atmos Tower

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0



## Workbook Case [Atms Tower]

The material stream results for the Workbook Case [Atms Tower] appear below.

Figure R1.16


Name	Reflux	To Condenser	Main Steam	Residue	4	Off Gas	Water draw
Vapour Fraction	0.0000	1.0000	1.0000	0.0000	0.6122	1.0000	0.0000
Temperature [F]	107.3	274.6	375.0	669.1	622.2	107.3	107.3
Pressure [psia]	19.70	28.70	150.0	32.70	65.00	19.70	19.70
Molar Flow [lbmole/hr]	2010	5532	416.3	1397	6214	4.473e+005	700.9
Mass Flow [lb/hr]	1.763e+005	4.363e+005	7500	6.216e+005	1.282e+006	2.304e+003	1.263e+004
Liquid Volume Flow [barrel/day]	1.638e+004	4.025e+004	514.6	4.398e+004	1.000e+005	2.612e+004	866.4
Heat Flow [Btu/hr]	-1.661e+008	-3.743e+008	-4.222e+007	-3.647e+008	-7.452e+008	-2.296	-8.561e+007
Name	Naphtha	Kero	Kero_SS_Draw	Kero_SS_Return	Kero_SS_BoilU	Kero_SS_ToRe	Diesel Steam
Vapour Fraction	0.0000	0.0000	0.0000	1.0000	1.0000	0.0000	1.0000
Temperature [F]	107.3	457.5	406.1	429.3	457.5	446.9	300.0
Pressure [psia]	19.70	29.84	29.84	29.84	29.84	29.84	50.00
Molar Flow [lbmole/hr]	2822	701.9	912.4	210.5	371.2	1073	166.5
Mass Flow [lb/hr]	2.474e+005	1.115e+005	1.397e+005	2.816e+004	5.561e+004	1.671e+005	3000
Liquid Volume Flow [barrel/day]	2.300e+004	9300	1.171e+004	2410	4681	1.398e+004	205.8
Heat Flow [Btu/hr]	-2.331e+008	-8.098e+007	-1.063e+008	-1.777e+007	-3.406e+007	-1.225e+008	-1.697e+007
Name	Diesel	Diesel_SS_Draw	Diesel_SS_Return	AGO	5	AGO_SS_Draw	AGO_SS_Return
Vapour Fraction	0.0000	0.0000	1.0000	0.0000	1.0000	0.0000	1.0000
Temperature [F]	486.8	512.1	504.9	571.6	300.0	615.4	602.9
Pressure [psia]	30.99	30.99	30.99	31.70	50.00	31.70	31.70
Molar Flow [lbmole/hr]	1114	1331	383.8	200.4	138.8	272.3	210.7
Mass Flow [lb/hr]	2.429e+005	2.800e+005	4.015e+004	5.945e+004	2500	7.563e+004	1.868e+004
Liquid Volume Flow [barrel/day]	1.925e+004	2.231e+004	3269	4500	171.5	5776	1448
Heat Flow [Btu/hr]	-1.722e+008	-1.931e+008	-3.788e+007	-3.882e+007	-1.414e+007	-4.685e+007	-2.217e+007
Name	PA_1_Draw	PA_1_Return	PA_2_Draw	PA_2_Return	PA_3_Draw	PA_3_Return	"" New ""
Vapour Fraction	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	
Temperature [F]	315.9	142.5	512.1	367.4	615.4	485.0	
Pressure [psia]	28.84	28.84	30.99	30.99	31.70	31.70	
Molar Flow [lbmole/hr]	4716	4716	1790	1790	1414	1414	
Mass Flow [lb/hr]	5.740e+005	5.740e+005	3.765e+005	3.765e+005	3.928e+005	3.928e+005	
Liquid Volume Flow [barrel/day]	5.000e+004	5.000e+004	3.000e+004	3.000e+004	3.000e+004	3.000e+004	
Heat Flow [Btu/hr]	-4.697e+008	-5.247e+008	-2.596e+008	-2.946e+008	-2.433e+008	-2.783e+008	







# R2 Sour Water Stripper



<b>R2.1 Process Description .....</b>	<b>3</b>
<b>R2.2 Introduction .....</b>	<b>4</b>
<b>R2.3 Setup .....</b>	<b>4</b>
<b>R2.4 Steady State Simulation .....</b>	<b>5</b>
R2.4.1 Installing the SW Stripper.....	5
<b>R2.5 Results .....</b>	<b>8</b>
<b>R2.6 Case Study.....</b>	<b>10</b>
R2.6.1 Results .....	12








## R2.1 Process Description

Figure R2.1




To see this case completely solved, see your HYSYS\Samples\ directory and open the **R-2.hsc** file.

The sour water stripper configuration shown in the above PFD is a common unit in refineries. It processes sour water that comes from a variety of sources including hydrotreaters, reformers, hydrocrackers and crude units. The sour water is often stored in crude tanks, thereby eliminating the need for special vapour recovery systems.

A sour water stripper either uses the direct application of stripping steam (usually low quality, low pressure) or a steam-fired reboiler as a heat source.

Figure R2.2





The intent is to drive as much H<sub>2</sub>S and NH<sub>3</sub> overhead in the stripper as possible. The sizing of a sour water stripper is very important since its capacity must equal or exceed the normal production rates of sour water from multiple sources in the refinery. Often, refiners find their strippers undersized due to a lack of allowance for handling large amounts of sour water, which can result from upset conditions (like start-up and shutdown). Consequently, there is often a backlog of sour water waiting to be processed in the stripper. With the increasing importance of environmental restrictions, the sour water stripper plays a greater role in the overall pollution reduction program of refiners.

## R2.2 Introduction

The Sour Water feed stream goes through a feed/effluent exchanger where it recovers heat from the tower bottoms stream (Stripper Bottoms). This new stream (Stripper Feed) enters on tray 3 of an 8 tray distillation tower with a reboiler and a total reflux condenser. A quality specification of 10 ppm wt. ammonia on the tower bottoms (Stripper Bottoms) is specified. The tower bottoms, Stripper Bottoms, exchanges heat with the incoming feed and exits as Effluent.

There are two basic steps in this process simulation:

1. **Setup.** This case uses the Sour Peng-Robinson package and the following components: H<sub>2</sub>S, NH<sub>3</sub> and H<sub>2</sub>O.
2. **Steady State Simulation.** The case will consist of an 8 stage stripper, used to separate H<sub>2</sub>S and NH<sub>3</sub>, and a heat exchanger to minimize heat loss.

## R2.3 Setup

1. Select the following components: **H<sub>2</sub>S, NH<sub>3</sub> and H<sub>2</sub>O.**
2. Select the **Sour Peng-Robinson** property package. It combines the PR equation of state and Wilson's API-Sour model for handling sour water systems.
3. Set the units to **Field** in the Session Preferences (Tools menu).



## R2.4 Steady State Simulation

The following general steps will be taken to setup this case in steady state:

1. **Installing the SW Stripper.** An 8 stage distillation column will be used to strip the sour components from the feed stream. The liquid leaving the bottom of the column heats the incoming feed stream in a heat exchanger.
2. **Case Study.** A case study will be performed to obtain steady state solutions for a range of stripper feed temperatures.

### R2.4.1 Installing the SW Stripper

#### Feed Stream

Specify the feed stream as shown below.

Material Stream [SourH2O Feed]	
In this cell...	Enter...
Temperature	100°F
Pressure	40 psia
Std Ideal Liq Vol Flow	50,000 barrel/day
Comp Mass Frac [H2S]	0.0070
Comp Mass Frac [NH3]	0.0050
Comp Mass Frac [H2O]	0.9880



## Operations

1. Install and specify the Heat Exchanger as shown below.

Heat Exchanger [Feed Bottoms]		
Tab[Page]	In this cell...	Enter...
<b>Design [Connections]</b>	Tube Side Inlet	Sour H2O Feed
	Tube Side Outlet	Stripper Feed
	Shell Side Inlet	Stripper Bottoms
	Shell Side Outlet	Effluent
<b>Design [Parameters]</b>	Heat Exchanger Model	Exchanger Design (Weighted)
	Tube Side Pressure Drop	10 psi
	Shell Side Pressure Drop	10 psi
<b>Worksheet [Conditions]</b>	Temperature (Stripper Feed)	200°F

2. Install a Distillation Column using the **Distillation Column** icon in the Object Palette. This column will have both a reboiler and an overhead condenser.
3. Define the Column configuration as shown below.

If messages appear regarding loading an older case or installing property sets, click the OK button. They will not affect the case.

Column [SW Stripper]		
Page	In this cell...	Enter...
<b>Connections</b>	No. of Stages	8
	Inlet Stream	Stripper Feed
	Inlet Stage	3
	Condenser Type	Full Reflux
	Overhead Vapour	Off Gas
	Bottoms Liquid	Stripper Bottoms
	Reboiler Energy Stream	Q-Reb
	Condenser Energy Stream	Q-Cond
<b>Pressure Profile</b>	Condenser Pressure	28.7 psia
	Reboiler Pressure	32.7 psia

4. In the Column property view, click the **Design** tab, then select the **Monitor** page.
5. Click the **Add Specs** button to install new specifications.


In the present configuration, the column has two degrees of freedom. For this example, the two specifications used will be a quality specification and a reflux ratio.



6. First, uncheck the **Active** checkbox for the Ovhd Vap Rate specification.
7. Add a Component Fraction specification and modify the existing Reflux Ratio specification and define as shown below.

Column [SW Stripper]		
Tab [Page]	In this cell...	Enter...
Design [Specs]	Liquid Mass Frac.	Active
	Stage	Reboiler
	Spec Value	0.000010
	Component	NH <sub>3</sub>
	Reflux Ratio	Active
	Spec Value	10 Molar

The specifications views should appear as follows.



For more information on which damping factor is recommended for different systems, refer to [Chapter 8 - Column](#) of the **Operations Guide**.

8. Click the **Parameters** tab, then select the **Solver** page. Change the Fixed Damping Factor to 0.4. A damping factor will speed up tower convergence and reduce the effects of any oscillations in the calculations (the default value is 1.0).
9. Click the **Run** button. The column will converge.



# R2.5 Results

## Workbook Case [Main]

### Materials Streams Tab

Figure R2.5

Name	SourH2O Feed	Stripper Feed	Stripper Bottom:	Effluent	Off Gas
Vapour Fraction	0.0000	0.0033	0.0000	0.0000	1.0000
Temperature [F]	100.0	200.0	255.3	152.7	210.9
Pressure [psia]	40.00	30.00	32.70	22.70	28.70
Molar Flow [lbmole/hr]	3.996e+004	3.996e+004	3.905e+004	3.905e+004	905.4
Mass Flow [lb/hr]	7.241e+005	7.241e+005	7.035e+005	7.035e+005	2.061e+004
Liquid Volume Flow [barrel/day]	5.000e+004	5.000e+004	4.827e+004	4.827e+004	1732
Heat Flow [Btu/hr]	-4.835e+009	-4.761e+009	-4.661e+009	-4.737e+009	-4.955e+007
Name	** New **				

Material Streams Compositions Energy Streams Unit Ops

FeederBlock\_SourH2O Feed  
Feed Bottoms

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0

### Compositions Tab

Figure R2.6

Name	SourH2O Feed	Stripper Feed	Stripper Bottom:
Comp Mass Frac (H2S)	0.0132	0.0132	0.0000
Comp Mass Frac (Ammonia)	0.0047	0.0047	0.0000
Comp Mass Frac (H2O)	0.9821	0.9821	1.0000
Name	Effluent	Off Gas	** New **
Comp Mass Frac (H2S)	0.0000	0.4625	
Comp Mass Frac (Ammonia)	0.0000	0.1648	
Comp Mass Frac (H2O)	1.0000	0.3727	

Material Streams Compositions Energy Streams Unit Ops


FeederBlock\_SourH2O Feed  
Feed Bottoms

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0



Energy Streams Tab

Figure R2.7





## R2.6 Case Study

The simulation can be run for a range of Stripper Feed temperatures (e.g. 190°F through 210°F in 5 degree increments) by changing the temperature specified for Stripper Feed in the worksheet.

You can automate these changes by using the Case Studies feature in the DataBook.

1. Open the DataBook property view (Tools menu).
2. On the **Variables** tab, enter the variables as shown below.


Flowsheet	Object	Variables	Variables Description
<b>Case</b>	Q-Cond	Heat Flow	Cooling Water
	Q-Reb	Heat Flow	Steam
	Stripper Feed	Temperature	Temperature
	Feed Bottoms	UA	UA
<b>T-100 SW Stripper</b>	Main TS	Stage Liq Net Mass Flow (2__Main TS)	Liq MF Tray 2
	Main TS	Stage Liq Net Mass Flow (7__Main TS)	Liq MF Tray 7
	Main TS	Stage Vap Net Mass Flow (2__Main TS)	Vap MF Tray 2
	Main TS	Stage Vap Net Mass Flow (7__Main TS)	Vap MF Tray 7

3. Click the **Case Studies** tab.
4. In the Available Case Studies group, click the **Add** button to create Case Study 1.



5. Check the Independent and Dependent Variables as shown below.


Figure R2.8



To automate the study, the Dependent Variable range and Step Size must be given.

6. Click the **View** button to access the Case Studies Setup view. Define the range and step size for the Stripper Feed Temperature as shown below.

Figure R2.9



Temperature values are given in °F.


7. To begin the Study, click the **Start** button.
8. Click the **Results** button to view the variables. If the results are in graphical form, click the **Table** radio button on the Case Studies view.



## R2.6.1 Results

The results of this study appear below.

Figure R2.10



Case Studies - Main


State	State 1	State 2	State 3	State 4	State 5
Stripper Feed - Temperature [F]	190.0	195.0	200.0	205.0	210.0
Cooling Water [Btu/hr]	1.515e+008	1.542e+008	1.568e+008	1.597e+008	1.626e+008
Steam [Btu/hr]	2.091e+008	2.080e+008	2.070e+008	2.059e+008	2.050e+008
Feed Bottoms - UA [Btu/F-hr]	1.054e+006	1.214e+006	1.408e+006	1.649e+006	1.959e+006
Liq MF Tray 2 [lb/hr]	1.584e+005	1.611e+005	1.640e+005	1.668e+005	1.698e+005
Liq MF Tray 7 [lb/hr]	9.229e+005	9.215e+005	9.202e+005	9.189e+005	9.175e+005
Vap MF Tray 2 [lb/hr]	1.783e+005	1.813e+005	1.844e+005	1.875e+005	1.908e+005
Vap MF Tray 7 [lb/hr]	2.178e+005	2.167e+005	2.156e+005	2.145e+005	2.135e+005

Case Study 1

☒ Table
 ☐ Graph



# P1 Propylene/Propane Splitter



<b>P1.1 Process Description.....</b>	<b>3</b>
<b>P1.2 Setup .....</b>	<b>4</b>
<b>P1.3 Steady State Simulation .....</b>	<b>5</b>
P1.3.1 Starting the Simulation .....	5
P1.3.2 Adding the Stripper (Reboiled Absorber) .....	6
P1.3.3 Adding the Rectifier (Refluxed Absorber) .....	7
P1.3.4 Adding the Specifications .....	8
<b>P1.4 Results .....</b>	<b>10</b>









# P1.1 Process Description

Figure P1.1



A propylene-propane splitter is generally an easy column to converge. The critical factor in producing good results, however, is not the ease of solution, but the accurate prediction of the relative volatility of the two key components. Special consideration was given to these components, and others, in developing the binary interaction coefficients for the Peng Robinson and Soave Redlich Kwong Equations of State to ensure that these methods correctly model this system.

Figure P1.2





These splitters have many stages and are often built as two separate columns. This simulation will contain two Columns, a Stripper, and a Rectifier. The Stripper is modeled as a Reboiled Absorber and contains 94 theoretical stages. The Rectifier is a Refluxed Absorber containing 89 theoretical stages. The Stripper contains two feed streams, one is the known stream, FEED, and the other is the bottoms from the Rectifier. Propane is recovered from the Stripper bottoms (95%) and Propene is taken off the top of the Rectifier (99%).

There are two basic steps in this process simulation:

1. **Setup.** The Soave Redlich Kwong (SRK) property package will be used and the component list includes Propane and Propene.
2. **Steady State Simulation.** The case will consist of a column divided into two tray sections: a Refluxed Absorber as a Rectifier and a Reboiled Absorber as a Stripper.

## P1.2 Setup

1. Create a new HYSYS case.
2. Set the unit preferences to Field. From the **Tools** menu, select **Preferences**. The Session Preferences view appears. On the **Variables** tab (Units page), select **Field** from the Available Unit Sets list. Close the Session Preferences view.
3. Create a component list containing Propane and Propene. It may be easier to search by chemical formula ( $C_3H_8$  and  $C_3H_6$ ), as the entire list is quite extensive. Once these components are selected, close the view.
4. Select the **Soave Redlich Kwong (SRK)** equation of state (EOS) as the property method for this case. Ensure that the selected component you just created appears in the Component List Selection drop-down list.



# P1.3 Steady State Simulation

The case will be setup in steady state using the Custom Column option. Both the Rectifier and Stripper columns will be built in the same column environment.

## P1.3.1 Starting the Simulation

### Defining the Feed Stream

In the Main Simulation environment, define the conditions and compositions of the Feed stream as shown in the following table.

This example uses Field units. If you need to change the units, go to the **Tools** menu and select the **Preferences** command. On the **Variables** tab, change your units to **Field**.

Set the Mole Fractions on the **Composition** page.

Material Stream [Feed]	
In this cell...	Enter...
Name	Feed
Vapour Frac	1.0
Pressure	300 psia
Molar Flow	1350 lbmole/hr
Comp Mole Frac [Propane]	0.4
Comp Mole Frac [Propene]	0.6

### Installing the Column

1. Click the **Custom Column** icon on the Object Palette. The Custom Column feature will be used to build both columns in a single column environment.
2. Click the **Start with a Blank Flowsheet** button. The column appears in the PFD.
3. Double-click the column in the PFD to open the Column view.
4. Click the **Design** tab and select the **Connections** page.
5. In the Inlet Streams group, enter stream **Feed** as an External Feed Stream, making this stream accessible to the Template Environment.
6. Enter the Column Environment by clicking the **Column Environment** button at the bottom of the Column property view.




For this example, you will need a Total Condenser, Reboiler and two Tray Sections. A Tray Section and a Condenser will be used for the Refluxed Absorber (Rectifier), a Reboiler and another Tray Section will be used for the Reboiled Absorber (Stripper). The overhead product from the Stripper will serve as the feed to the Rectifier, and the bottoms product from the Rectifier provides a second feed to the Stripper, entering at Stage 1.

## P1.3.2 Adding the Stripper (Reboiled Absorber)

Install the Reboiled Absorber before the Reboiler. This column has 94 ideal stages and a Reboiler.

Ensure that you are within the Column Environment; the PFD view and the Column Object Palette should be visible (as shown on the left).



Column Object Palette



Tray Section icon

Define the Number of Trays on the Parameters page first.

### Installing the Tray Section

For this Column a new Tray Section has to be installed.

1. Double-click the **Tray Section** icon on the Object Palette. The tray section appears in the PFD and the Tray Section property view appears.
2. Supply the following information.

Tray Section [Stripper]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Column Name	Stripper
	Liquid Inlet	Rect Out
	Vapour Inlet	Boilup
	Vapour Outlet	To Rect
	Liquid Outlet	To Reboiler
	Optional Feed Streams	Feed (Stage 47)
Design [Parameters]	Number of Trays	94
Design [Pressures]	Tray 1	290 psia
	Tray 94	300 psia

3. Close the Tray Section view.



## Installing the Reboiler

The Reboiler for the Absorber must be installed with the Stripper Column.

1. Double-click the **Reboiler** icon on the Object Palette. The Reboiler appears in the PFD and the Reboiler property view appears.
2. Enter the following information.



Reboiler icon

Reboiler [Reboiler]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Name	Reboiler
	Boilup	Boilup
	Inlets	To Reboiler
	Bottoms Outlet	Propane
	Energy	Reboiler Duty

## P1.3.3 Adding the Rectifier (Refluxed Absorber)

Next, you will install the Rectifier. This column has 89 ideal stages and a Total Condenser.

## Installing the Tray Section

Install a new Tray Section for the Absorber.

1. Double-click the **Tray Section** icon on the Object Palette. The tray section appears in the PFD and the Tray Section property view appears.
2. Supply the parameters as shown below.

Tray Section [Rectifier]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Name	Rectifier
	Liquid Inlet	Reflux
	Vapour Inlet	To Rect
	Vapour Outlet	To Condenser
	Liquid Outlet	Rect Out
Design [Parameters]	Number of Trays	89



**Tray Section [Rectifier]**

<b>Design [Pressures]</b>	Tray 1	280 psia
	Tray 89	290 psia

3. Close the Tray Section view.

## Installing the Total Condenser

A Total Condenser is required for the column.



Total Condenser icon

1. Double-click the **Total Condenser** icon in the Object Palette. The condenser icon appears in the PFD, and the condenser property view appears.
2. Supply the following information.

**Total Condenser [Condenser]**

Tab [Page]	In this cell...	Enter...
<b>Design [Connections]</b>	Name	Condenser
	Inlets	To Condenser
	Distillate	Propene
	Reflux	Reflux
	Energy	Condenser Duty

## P1.3.4 Adding the Specifications

Two specifications are required for this column.

1. Flow of the Rectifier Distillate (Propene) is 775 lbmole/hr.
2. Rectifier Top Stage Reflux Ratio is 16.

## Adding the Distillate Rate Specification

First you will add the Propene Distillate Rate specification.

1. Return to the Parent environment and ensure the Column property view is visible.
2. Click the **Design** tab and select **Monitor** page.
3. Click the **Add Spec** button. The Add Specs view appears.



4. In the Add Specs view, select **Column Draw Rate**, then click the **Add Spec(s)** button.
5. In the **Draw** cell, select Propene as the associated stream.
6. In the Spec Value cell, enter 775 lbmole/hr.


## Adding the Reflux Rate Specification

Next you will add the Rectifier Top Stage Reflux specification using a slightly different procedure than what you used to add the Distillate Rate Specification. This is only to show you another way to add specifications.

1. Click the **Design** tab, then select the **Specs** page.
2. In the Column Specifications group, click the **Add** button. The Add Specs view appears.
3. In the Add Specs view, select **Column Reflux Ratio**, then click the **Add Spec(s)** button. The Reflux Ratio Spec view appears.
4. In the **Stage** cell, select Condenser. In the **Flow Basis** cell, select Molar. In the **Spec Value** cell, enter 16.4.

The specification views should appear as shown below.

Figure P1.3



If the column has not converged at this point, ensure the Run Column Solver icon is active.



Run Column Solver icon (green)

Hold Column Solver icon (red)



# P1.4 Results

## Workbook T-100 (COL1)

### Material Streams Tab

Figure P1.4

Workbook - T-100 (COL1)					
Name	Feed	Rect Out	Boilup	To Rect	To Reboiler
Vapour Fraction	1.0000	0.0000	1.0000	1.0000	0.0000
Temperature [F]	126.7	121.1	135.1	121.1	135.0
Pressure [psia]	300.0	290.0	300.0	290.0	300.0
Molar Flow [lbmole/hr]	1350	1.294e+004	1.284e+004	1.372e+004	1.341e+004
Mass Flow [lb/hr]	5.790e+004	5.502e+005	5.639e+005	5.828e+005	5.892e+005
Liquid Volume Flow [barrel/day]	7698	7.276e+004	7.604e+004	7.705e+004	7.945e+004
Heat Flow [Btu/hr]	-1.729e+007	-1.048e+008	-5.158e+008	-3.209e+007	-6.060e+008
Name	Propane	Reflux	To Condenser	Propene	** New **
Vapour Fraction	0.0000	0.0000	1.0000	0.0000	
Temperature [F]	135.1	116.0	116.0	116.0	
Pressure [psia]	300.0	280.0	280.0	280.0	
Molar Flow [lbmole/hr]	574.9	1.271e+004	1.349e+004	775.1	
Mass Flow [lb/hr]	2.527e+004	5.352e+005	5.678e+005	3.263e+004	
Liquid Volume Flow [barrel/day]	3408	7.036e+004	7.465e+004	4290	
Heat Flow [Btu/hr]	-2.626e+007	3.350e+007	1.064e+008	2.043e+006	
Material Streams   Compositions   Energy Streams   Unit Ops					
Feed @Main Stripper					
<input type="checkbox"/> Show Name Only Number of Hidden Objects: 0					

### Compositions Tab


Figure P1.5

Workbook - T-100 (COL1)					
Name	Feed	Rect Out	Boilup	To Rect	To Reboiler
Comp Mole Frac (Workbook) (Pr	0.4000	0.2145	0.9153	0.2029	0.9157
Comp Mole Frac (Workbook) (Pr	0.6000	0.7855	0.0847	0.7971	0.0843
Name	Propane	Reflux	To Condenser	Propene	** New **
Comp Mole Frac (Workbook) (Pr	0.9251	0.0105	0.0105	0.0105	
Comp Mole Frac (Workbook) (Pr	0.0749	0.9895	0.9895	0.9895	
Material Streams   Compositions   Energy Streams   Unit Ops					
Feed @Main Stripper					
<input type="checkbox"/> Show Name Only Number of Hidden Objects: 0					



# Energy Streams Tab

Figure P1.6









# C1 Ethanol Plant

<b>C1.1 Process Description .....</b>	<b>3</b>
<b>C1.2 Setup .....</b>	<b>6</b>
<b>C1.3 Steady State Simulation .....</b>	<b>6</b>
C1.3.1 Adding Streams.....	6
C1.3.2 Installing Equipment.....	7
C1.3.3 Draw Stream Location.....	12
<b>C1.4 Results .....</b>	<b>13</b>








# C1.1 Process Description

Figure C1.1




Ethanol and Water form an azeotropic mixture at 1 atm. Therefore, with simple distillation, the ethanol and water mixture can only be concentrated up to the azeotropic concentration.

Typically, an ethanol fermentation process produces mainly Ethanol plus small quantities of several by-products: methanol, 1-propanol, 2-propanol, 1-butanol, 3-methyl-1-butanol, 2-pentanol, acetic acid, and CO<sub>2</sub>.

The CO<sub>2</sub> produced in the fermentation vessel carries some ethanol. This CO<sub>2</sub> stream is washed with water in a vessel (CO<sub>2</sub> Wash) to recover the Ethanol, which is recycled to the fermentor.

Figure C1.2






Fusel oils are a mixture of propanols, butanols and pentanols that have a potential value superior to that of ethanol. Accumulation of fusel oils in the Rectification Tower can cause the formation of a second liquid phase and subsequent deterioration of performance for these trays, so small side liquid draws of fusel oils are installed on the rectifier to avoid this problem.

The Ethanol rich product stream from the fermentor is sent to a concentration (Conc) tower. An absorber with a side vapour draw can be used to represent this tower.

The top vapour is fed to a light purification tower (Lights) where most of the remaining CO<sub>2</sub> and some light alcohols are vented. The bottom product of this light tower is fed to the Rectifier.


Figure C1.3



The side vapour draw from the Concentrator is the main feed for the Rectifier. The Rectifier is operated as a conventional distillation tower. The product of this tower is taken from Stage 2 so to have an azeotropic ethanol product with a lesser methanol contamination. Methanol concentrates towards the top stages, so a small distillate draw is provided at the condenser. Also, a small vent for CO<sub>2</sub> is provided at the condenser.



Figure C1.4



Another factor of interest is the concentration of heavy alcohols in the interior of the Rectifier. These alcohols are normally referred to as Fusel oils, and a small side liquid draw is provided in the Rectifier to recover these components.

There are two general steps in this process simulation:

1. **Setup.** The NRTL property package and the UNIFAC VLE estimation method will be used for this case. The Components list includes Ethanol, H<sub>2</sub>O, CO<sub>2</sub>, Methanol, Acetic Acid, 1- Propanol, 2-Propanol, 1-Butanol, 3-M-1-C4ol, 2-Pentanol and Glycerol.
2. **Steady State Simulation.** This case will use a separator, two absorbers, a refluxed absorber and a distillation column.



## C1.2 Setup

From the **Tools** menu, select **Preferences**.

Click the **Variables** tab, then select the **Units** page.

Select **SI** from the Available Unit Sets list, then close the view.

1. In a new HYSYS case, set the units to **SI**.
2. Select the following components: Ethanol, H<sub>2</sub>O, CO<sub>2</sub>, Methanol, Acetic Acid, 1- Propanol, 2-Propanol, 1-Butanol, 3-M-1-C<sub>4</sub>ol, 2-Pentanol and Glycerol.
3. Select NRTL as the Property Package.
4. On the **Binary Coeffs** tab (Fluid Package property view), select the **UNIFAC VLE** radio button, then click the **Unknowns Only** button to estimate the missing interaction parameters.

## C1.3 Steady State Simulation

### C1.3.1 Adding Streams

Enter the Simulation environment and add the material streams defined below.

Once you have entered the Mole Fractions for the stream FromFerm, the Mole Fractions will not add up to 1.00. Click the **Normalize** button and the total Mole Fraction will equal 1.00.

Name	Wash H2O	FromFerm	Steam A
In this cell...	Enter...	Enter...	Enter...
Temperature [C]	25	30	140
Pressure [kPa]	101.3250	101.3250	101.3250
Molar Flow [kgmole/hr]	130	2400	
Mass Flow [kg/hr]			11000
Comp Mole Frac [Ethanol]	0.0000	0.0269	0.0000
Comp Mole Frac [H <sub>2</sub> O]	1.0000	0.9464	1.0000
Comp Mole Frac [CO <sub>2</sub> ]	0.0000	0.0266	0.0000
Comp Mole Frac [Methanol]	0.0000	2.693e-05	0.0000
Comp Mole Frac [Acetic Acid]	0.0000	3.326e-06	0.0000
Comp Mole Frac [1-Propanol]	0.0000	9.077e-06	0.0000
Comp Mole Frac [2-Propanol]	0.0000	9.096e-06	0.0000
Comp Mole Frac [1-Butanol]	0.0000	6.578e-06	0.0000
Comp Mole Frac [3-M-1-C <sub>4</sub> ol]	0.0000	2.148e-05	0.0000
Comp Mole Frac [2-Pentanol]	0.0000	5.426e-06	0.0000
Comp Mole Frac [Glycerol]	0.0000	6.64e-06	0.0000



## C1.3.2 Installing Equipment

### CO<sub>2</sub> Vent Separator

The CO<sub>2</sub>Vent Separator separates the products from the fermentor. The bottom liquid of the separator is sent to the distillation section of the plant (Concentrator Tower), while the overhead vapour goes to the CO<sub>2</sub>Wash Tower.

Install a Separator and make the connections shown below.

SEPARATOR [CO <sub>2</sub> Vent]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlets	FromFerm
	Vapour Outlet	To CO <sub>2</sub> Wash
	Liquid Outlet	Beer

### CO<sub>2</sub> Wash Tower

Water is used to strip any Ethanol entrained in the off gas mixture, thus producing an overhead of essentially pure CO<sub>2</sub>. The bottom product from the tower is recycled to the Fermentor, however, the recycle is not a concern in this example.

- Before installing the column, select Preferences from the HYSYS Tools menu. On the Options page of the Simulation tab, ensure that the **Use Input Experts** checkbox is checked, then close the view.
- Install the CO<sub>2</sub> Wash Tower as a simple Absorber.

Absorber [CO <sub>2</sub> WASH]		
Tab [Page]	In this cell...	Enter...
Connections	No. of Stages	10
	Top Stage Inlet	Wash H <sub>2</sub> O
	Bottom Stage Inlet	To CO <sub>2</sub> Wash
	Ovhd Vapour	CO <sub>2</sub> Stream
	Bottoms Liquid	To fermentor
Pressure Profile	Top Stage	101.325 kPa
	Bottom Stage	101.325 kPa



- Click the **Run** button in the Column property view to calculate the CO<sub>2</sub> Wash Tower product streams.

## Concentrator

- Install the Concentrator as an Absorber with a side vapour draw.

Absorber [CONC]		
Tab [Page]	In this cell...	Enter...
Connections	No. of Stages	17
	Top Stage Inlet	Beer
	Bottom Stage Inlet	Steam A
	Ovhd Vapour	To Light
	Bottoms Liquid	Stillage A
	Side Draw Vapour	Rect Feed (Stage 6)
Pressure Profile	Condenser	101.325 kPa
	Reboiler	102.325 kPa
Temperature Estimates	Condenser Temperature	90°C
	Reboiler Temperature	110°C

- Create and define the following specifications to fully specify the column.

You might have to deactivate the default Rect Feed Rate specification to converge the column.

Specifications		
Tab [Page]	In this cell...	Enter...
Design [Specs]	Comp Recovery	Active
	Draw	Rect Feed
	SpecValue	0.95
	Component	Ethanol
	Draw Rate 1	Estimate
	Draw	Rect Feed
	Flow Basis	Mass
	Spec Value	5000 kg/h
	Draw Rate 2	Estimate
	Draw	To_Light
	Flow Basis	Molar
	Spec Value	1000 kgmole/h

- Click the **Run** button in the Column property view to calculate the Concentrator product streams.



## Lights

1. Add the Lights Tower purification tower, modeled as a Refluxed Absorber, and define as indicated below.

Refluxed Absorber [Lights]		
Tab [Page]	In this cell...	Enter...
<b>Connections</b>	No. of Stages	5
	Bottom Inlet Streams	To Light
	Condenser Type	Partial
	Ovhd Vapour	Light Vent
	Ovhd Liquid	2ndEtOH
	Bottoms Liquid	To Rect
	Cond. Energy	CondDuty
<b>Pressure Profile</b>	Condenser Pressure	101.325 kPa
	Reboiler Pressure	101.325 kPa

2. Delete the default **Btms Prod Rate** and **Reflux Rate** specifications from the Column Specification group.
3. Add the following new column specifications (**Design** tab, **Specs** page).

Specifications		
Tab [Page]	In this cell...	Enter...
<b>Design [Specs]</b>	Vap Prod Rate	Active
	Draw	Light_Vent
	Flow Basis	Molar
	Spec Value	1.6 kgmole/hr
	Comp Fraction	Active
	Stage	Condenser
	Flow Basis	Mass Fraction
	Phase	Liquid
	Spec Value	0.88
	Component	Ethanol
	Reflux Ratio	Estimate
	Stage	Condenser
	Flow Basis	Molar
	Spec Value	5.00
	Distillate Rate	Estimate
	Draw	2ndEtOH
	Flow Basis	Molar
	Spec Value	2.10 kgmole/hr



4. If required, click the **Run** button in the Column property view to calculate the Light Tower product streams.

## Rectifier

The primary product from a plant such as this would be the azeotropic mixture of ethanol and water. The Rectifier serves to concentrate the water/ethanol mixture to near azeotropic composition. The Rectifier is operated as a conventional distillation tower. It contains a partial condenser as well as a reboiler.

1. Add the Rectifier column, modeled as a distillation tower, and define it using the following information.

Column [RECT]		
Tab [Page]	In this cell...	Enter...
<b>Connections</b>	No. of Stages	29
	Inlet Streams [Stage]	To Rect [19] Rect_Feed [22]
	Condenser Type	Partial
	Ovhd Vapour	Rect Vap
	Ovhd Liquid	Rect Dist
	Bottoms Liquid	Stillage B
	Reboiler Energy	Rect RebQ
	Condenser Energy	Rect CondQ
	Side Draw Liquid [Stage]	1st Prod [2] Fusel [20]
<b>Pressure Profile</b>	Condenser Pressure	101.325 kPa
	Reboiler Pressure	101.325 kPa
<b>Temperature Estimates</b>	Condenser	79°C
	Reboiler	100°C

2. Delete the default **Btms Prod Rate** and **Reflux Rate** specifications before adding the new specifications. Delete all specifications that do not appear in the following table.



3. Define the following specifications (**Design** tab, **Specs** page). Also, set the damping factor to accelerate the convergence.

Specifications		
Tab [Page]	In this cell...	Enter...
<b>Design [Specs]</b>	Reflux Ratio	Active
	Stage	Condenser
	Flow Basis	Molar
	Spec Value	7100
	Ovhd Vap Rate	Active
	Draw	Rect_Vap
	Flow Basis	Molar
<b>Design [Specs]</b>	Spec Value	0.100 kgmole/hr
	Draw Rate	Active
	Draw	Rect _Dist
	Flow Basis	Mass
	Spec Value	2.00 kg/hr
	Comp Frac	Active
	Stage	2_Main TS
<b>Design [Specs]</b>	Flow Basis	Mass Fraction
	Phase	Liquid
	Spec Value	0.95
	Component	Ethanol
	Fusel Draw Rate	Active
	Draw	Fusel
	Flow Basis	Mass
<b>Design [Specs]</b>	Spec Value	3.00 kg/hr
	1stProd Draw Rate	Estimate
	Draw	1stProd
	Flow Basis	Molar
	Spec Value	68.00 kgmole/hr
<b>Parameters [Solver]</b>	Damping Factor	0.25
	Fixed	
	Azeotrope Check	ON

4. Click the **Run** button to solve the column.




## C1.3.3 Draw Stream Location

The side liquid draw, Fusel, is added at stage 20. To determine if this is an appropriate stage to recover the heavy alcohols, view the stage-by-stage composition profile.

1. To examine this information, click the **Parameters** tab in the Column property view.
2. Select the **Estimates** page. In this view you can see the Composition Estimates of each tray.

Figure C1.5



3. To view the 1-Propanol composition on Tray 20, scroll through the group until you can see Tray 20 and the 1-Propanol component.

Stage 20 has a high concentration of 1-Propanol (which has the greatest concentration among the heavy alcohols). Therefore, we have selected the appropriate stage for the Fusel draw.



# C1.4 Results

## Workbook Case (Main)

### Material Streams Tab

Figure C1.6

Name	Wash H2O	FromFerm	Steam A	To CO2 Wash	Beer	CO2 Stream
Vapour Fraction	0.0000	0.0277	1.0000	1.0000	0.0000	1.0000
Temperature [C]	25.00	30.00	140.0	30.00	30.00	26.06
Pressure [kPa]	101.3	101.3	101.3	101.3	101.3	101.3
Molar Flow [kgmole/h]	130.0	2400	610.6	66.47	2334	64.72
Mass Flow [kg/h]	2342	4.672e+004	1.100e+004	2857	4.386e+004	2792
Liquid Volume Flow [m3/h]	2.347	48.16	11.02	3.454	44.70	3.375
Heat Flow [kJ/h]	-3.704e+007	-6.892e+008	-1.448e+008	-2.557e+007	-6.636e+008	-2.515e+007

Name	To Fermenter	To Light	Stillage A	Rect Feed	Light Vent	2nd EtOH
Vapour Fraction	0.0000	1.0000	0.0000	1.0000	1.0000	0.0000
Temperature [C]	33.34	85.89	100.3	94.82	46.40	46.40
Pressure [kPa]	101.3	101.3	102.3	101.6	101.3	101.3
Molar Flow [kgmole/h]	131.8	10.03	2617	316.6	1.600	2.687
Mass Flow [kg/h]	2407	301.9	4.716e+004	7402	68.89	104.8
Liquid Volume Flow [m3/h]	2.426	0.3511	47.25	8.126	8.379e-002	0.1285
Heat Flow [kJ/h]	-3.745e+007	-2.556e+006	-7.308e+008	-7.506e+007	-5.678e+005	-7.444e+005

Name	To Rect	Rect Vap	Rect Dist	Stillage B	1st Prod	Fusel
Vapour Fraction	0.0000	1.0000	0.0000	0.0000	0.0000	0.0000
Temperature [C]	80.85	78.01	78.01	99.73	78.09	83.39
Pressure [kPa]	101.3	101.3	101.3	101.3	101.3	101.3
Molar Flow [kgmole/h]	5.742	0.1000	4.653e-002	253.1	69.04	8.660e-002
Mass Flow [kg/h]	128.2	4.306	2.000	4566	2955	3.000
Liquid Volume Flow [m3/h]	0.1388	5.360e-003	2.489e-003	4.578	3.675	3.541e-003
Heat Flow [kJ/h]	-1.602e+006	-2.324e+004	-1.261e+004	-7.068e+007	-1.871e+007	-2.435e+004

Material Streams Compositions Energy Streams Unit Ops

FeederBlock\_Wash H2O  
CO2 Wash

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0



# Compositions Tab

Figure C1.7

Workbook - Case (Main)						
Name	Wash H2O	FromFerm	Steam A	To CO2 Wash	Beer	CO2 Stream
Comp Mole Frac (Ethanol)	0.0000	0.0269	0.0000	0.0170	0.0272	0.0000
Comp Mole Frac (H2O)	1.0000	0.9464	1.0000	0.0409	0.9722	0.0333
Comp Mole Frac (CO2)	0.0000	0.0266	0.0000	0.9421	0.0005	0.9667
Comp Mole Frac (Methanol)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (AceticAcid)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (1-Propanol)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (2-Propanol)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (1-Butanol)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (3-M-1-C4ol)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (2-Pentanol)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (Glycerol)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Name	To Fermentor	To Light	Stillage A	Rect Feed	Light Vent	2ndEtOH
Comp Mole Frac (Ethanol)	0.0086	0.3164	0.0000	0.1903	0.1890	0.7451
Comp Mole Frac (H2O)	0.9910	0.5610	1.0000	0.8091	0.0517	0.2524
Comp Mole Frac (CO2)	0.0005	0.1213	0.0000	0.0000	0.7589	0.0007
Comp Mole Frac (Methanol)	0.0000	0.0002	0.0000	0.0002	0.0001	0.0004
Comp Mole Frac (AceticAcid)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (1-Propanol)	0.0000	0.0003	0.0000	0.0001	0.0001	0.0006
Comp Mole Frac (2-Propanol)	0.0000	0.0003	0.0000	0.0001	0.0002	0.0008
Comp Mole Frac (1-Butanol)	0.0000	0.0001	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (3-M-1-C4ol)	0.0000	0.0001	0.0000	0.0002	0.0000	0.0000
Comp Mole Frac (2-Pentanol)	0.0000	0.0003	0.0000	0.0000	0.0000	0.0001
Comp Mole Frac (Glycerol)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Name	To Rect	Rect Vap	Rect Dist	Stillage B	1st Prod	Fusel
Comp Mole Frac (Ethanol)	0.1513	0.8893	0.8886	0.0002	0.8826	0.2969
Comp Mole Frac (H2O)	0.8473	0.1057	0.1090	0.9995	0.1163	0.5305
Comp Mole Frac (CO2)	0.0000	0.0024	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (Methanol)	0.0001	0.0034	0.0022	0.0000	0.0009	0.0001
Comp Mole Frac (AceticAcid)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (1-Propanol)	0.0003	0.0000	0.0000	0.0000	0.0000	0.1338
Comp Mole Frac (2-Propanol)	0.0001	0.0002	0.0002	0.0000	0.0003	0.0003
Comp Mole Frac (1-Butanol)	0.0003	0.0000	0.0000	0.0001	0.0000	0.0035
Comp Mole Frac (3-M-1-C4ol)	0.0002	0.0000	0.0000	0.0002	0.0000	0.0000

Material Streams
**Compositions**
Energy Streams
Unit Ops

FeederBlock\_Wash H2O  
CO2 Wash

☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0



Energy Streams Tab

Figure C1.8

Name	CondDuty	Rect Reb Q	Rect CondQ
Heat Flow [kJ/h]	3.584e+005	2.764e+007	4.043e+007
Name	New		
Heat Flow [kJ/h]			

Material Streams   Compositions   **Energy Streams**   Unit Ops

Lights


☐ Include Sub-Flowsheets  
☐ Show Name Only  
Number of Hidden Objects: 0







# C2 Synthesis Gas Production



<b>C2.1 Process Description .....</b>	<b>3</b>
<b>C2.2 Setup .....</b>	<b>4</b>
C2.2.1 Components & Fluid Package .....	4
C2.2.2 Defining the Reactions .....	5
<b>C2.3 Steady State Simulation .....</b>	<b>9</b>
C2.3.1 Building the Flowsheet .....	10
C2.3.2 Installing Adjust Operations.....	14
<b>C2.4 Results .....</b>	<b>16</b>








## C2.1 Process Description

Figure C2.1



The production of synthesis gas is an important part of the overall process of synthesizing ammonia. The conversion of natural gas into the feed for the ammonia plant is modeled using three conversion reactions and an equilibrium reaction. To facilitate the production of ammonia, the molar ratio of hydrogen to nitrogen in the synthesis gas is controlled near 3:1. This ratio represents the stoichiometric amounts of the reactants in the ammonia process.

In a typical synthesis gas process, four reactors are needed. This model requires five reactors since the conversion and equilibrium reactions cannot be placed in the same reaction set and thus cannot be placed in the same reactor. The Combustor is separated into a conversion reactor and an equilibrium reactor.

Desulfurized natural gas is the source of hydrogen in this example, which is reformed in a conversion reactor (Reformer) when combined with steam. Air is added to the second reactor at a controlled flow rate such that the desired ratio of H<sub>2</sub>:N<sub>2</sub> in the synthesis gas is attained.



The oxygen from the air is consumed in an exothermic combustion reaction while the inert nitrogen passes through the system. The addition of steam serves the dual purpose of maintaining the reactor temperature and ensuring that the excess methane from the natural gas stream is consumed. In the last two reactors, the water-gas shift equilibrium reaction takes place as the temperature of the stream is successively lowered.

There are two general steps in this process simulation:

1. **Setup.** In this step the Fluid package, Reaction sets and Reaction components are selected. The Reaction Component list includes CH<sub>4</sub>, H<sub>2</sub>O, CO, CO<sub>2</sub>, H<sub>2</sub>, N<sub>2</sub> and O<sub>2</sub>.
2. **Steady State Simulation.** The case will be built in steady state with the following key unit ops:
  - **Reformer.** A conversion reactor in which most of the methane is reacted with steam to produce hydrogen, carbon monoxide and carbon dioxide.
  - **Combustor.** A second conversion reactor, which takes the product of the Reformer, an Air stream and a Comb. Steam stream as the feeds to the reactor.
  - **Shift Reactors.** A series of equilibrium reactors in which the water gas shift reaction occurs.

## C2.2 Setup

1. From the **Tools** menu, select **Preferences**.
2. In the Session Preferences view, **Variables** tab, **Units** page, select **Field** units for this application.
3. Close the Session Preferences view.

### C2.2.1 Components & Fluid Package

1. Create a new component list and add the following components: methane, water, carbon monoxide, carbon dioxide, hydrogen, nitrogen and oxygen.
2. Create a fluid package defined as **Peng-Robinson**.
3. On the Fluid Package view, click the **Rxns** tab, add the Global Rxn set, then close the Fluid Package view.



## C2.2.2 Defining the Reactions

Refer to [Chapter 5 - Reactions](#) in the **Simulation Basis** manual for more information about how to define reactions and reaction sets.

The **Rxn Components** group only shows the components associated with the Fluid Package(s).


To add or edit components, select the Add Comps button. The new components will automatically be added to any fluid package that uses the reaction.

On the Reactions tab of the Simulation Basis Manager, you can define the required reactions and attach them to reaction sets.

### Selecting Reaction Components

The reaction components are attached based on the associated fluid package and are listed in the Rxn Components group.

**Figure C2.2**





## Defining Reactions

In this example, there are three conversion reactions and one equilibrium reaction.

### Conversion Reactions

The reforming reactions are as follows:



The combustion reaction is as follows:



### Equilibrium Reaction

You can also define reactions and attach reaction sets in the Main Environment by selecting Reaction Package under Flowsheet in the main menu.

The water-gas shift reaction is as follows:





1. Add the two reforming reactions and input the following data:


Reaction [Rxn-1]		
Reactions View	Type	Conversion
Tab	In this cell...	Enter...
Stoichiometry	Component (Stoich. Coeff.)	Methane (-1)
		Water (-1)
		CO (1)
		Hydrogen (3)
Basis	Base Component	Methane
	Rxn Phase	VaporPhase
	Conversion	40% (Co)
Comments	$\text{CH}_4 + \text{H}_2\text{O} \rightarrow \text{CO} + 3\text{H}_2$	

Reaction [Rxn-2]		
Reactions View	Type	Conversion
Tab	In this cell...	Enter...
Stoichiometry	Component (Stoich. Coeff.)	Methane (-1)
		Water (-2)
		CO <sub>2</sub> (1)
		Hydrogen (4)
Basis	Base Component	Methane
	Rxn Phase	VaporPhase
	Conversion	30% (Co)
Comments	$\text{CH}_4 + 2\text{H}_2\text{O} \rightarrow \text{CO}_2 + 4\text{H}_2$	

2. Add the combustion and equilibrium reactions and input the following data:

Reaction [Rxn-3]		
Reactions View	Type	Conversion
Tab	In this cell...	Enter...
Stoichiometry	Component (Stoich. Coeff.)	Methane (-1)
		Oxygen (-2)
		CO <sub>2</sub> (1)
		Water (2)
Basis	Base Component	Methane
	Rxn Phase	VaporPhase
	Conversion	100%
Comments	$\text{CH}_4 + 2\text{O}_2 \rightarrow \text{CO}_2 + 2\text{H}_2\text{O}$	

Reaction [Rxn-4]		
Reactions View	Type	Equilibrium
Tab	Reaction	
Library	$\text{CO} + \text{H}_2\text{O} = \text{CO}_2 + \text{H}_2$	



1. To add the Equilibrium reaction, click the **Add Rxn**, button. The Reactions view appears.
2. From the Reactions list, select **Equilibrium**, then click the **Add Reaction** button. The Equilibrium Reaction view appears.
3. Click the **Library** tab.
4. In the Library Equilibrium Rxns group, select  $\text{CO} + \text{H}_2\text{O} = \text{CO}_2 + \text{H}_2$ , then click the **Add Library Rxn** button. HYSYS provides the equilibrium data and all other pertinent information for the reaction.



## Defining Reaction Sets


In the table of reaction sets, RXN-1 and RXN-2 appear in both the first and second reaction sets.

In HYSYS, each reactor operation may have only one reaction set attached to it, however, a reaction may appear in multiple reaction sets. In this case, you only have to provide three reaction sets for all five reactors.


In the Reaction Sets group, click the **Add Set** button to add new reaction sets. Define the following reactions sets. Select the following reactions in the Active List group as indicated.

Reaction Set Name	Active Reactions
Reformer Rxn Set	Rxn-1, Rxn-2
Combustor Rxn Set	Rxn-1, Rxn-2, Rxn-3
Shift Rxn Set	Rxn-4

Figure C2.3



## Attaching Reaction Sets to the Fluid Package



1. On the **Reactions** tab of the Simulation Basis Manager, select a Reaction Set, then click the **Add to FP** button. The Add view appears.
2. Select a fluid package from the list, then click the **Add Set to Fluid Package** button.
3. Repeat the procedure for the other two reaction sets.
4. Click the **Enter Simulation Environment** button.



## C2.3 Steady State Simulation

### Installing Streams

Here you will define the two feed streams to the first reactor (Natural Gas and Reformer Steam). The Comb. Steam stream and the Air stream will also be defined. The pressures of the steam and air streams will be specified later using SET operations. Install and define the streams as indicated.

Name	Natural Gas	Reformer Steam	Air	Comb. Steam
Temperature[F]	700.0	475.0	60.0	475.0
Pressure [psia]	500.0	<empty>	<empty>	<empty>
Molar Flow [lbmole/hr]	200.0	520.0	200.0**	300.0**
Comp Mole Frac [CH <sub>4</sub> ]	1.0000	0.0000	0.0000	0.0000
Comp Mole Frac [H <sub>2</sub> O]	0.0000	1.0000	0.0000	1.0000
Comp Mole Frac [CO]	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac [CO <sub>2</sub> ]	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac [H <sub>2</sub> ]	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac [N <sub>2</sub> ]	0.0000	0.0000	0.7900	0.0000
Comp Mole Frac [O <sub>2</sub> ]	0.0000	0.0000	0.2100	0.0000
<b>COMMENTS:</b> ** signifies initialized values; the molar flows of <b>Air</b> and <b>Comb. Steam</b> will be manipulated by <b>Adjust-2</b> and <b>Adjust-1</b> respectively.				



## C2.3.1 Building the Flowsheet

### Set Operations

An alternative method for setting the steam and air pressures is to import the Natural Gas pressure to a Spreadsheet, copy the value for each of the other streams and export the copied values to the streams

Install the following Set operations to specify the pressures of the steam and air streams. Install these before installing the Reformer so the reactor is calculated when you install it.

Set [SET-1]		
Tab	In this cell...	Enter...
Connections	Target Object	Reformer Steam
	Target Variable	Pressure
	Source Object	Natural Gas
Parameters	Multiplier	1
	Offset	0

Set [SET-2]		
Tab	In this cell...	Enter...
Connections	Target Object	Comb. Steam
	Target Variable	Pressure
	Source Object	Natural Gas
Parameters	Multiplier	1
	Offset	0

Set [SET-3]		
Tab	In This Cell...	Enter
Connections	Target Object	Air
	Target Variable	Pressure
	Source Object	Natural Gas
Parameters	Multiplier	1
	Offset	0



## Installing the Reformer

The Reformer is a conversion reactor in which most of the methane is reacted with steam to produce hydrogen, carbon monoxide, and carbon dioxide. The outlet gas will also contain the unreacted methane and excess water vapour from the steam. The overall conversion of the two reactions in the Reformer is 70%. Rxn-1, which produces carbon monoxide and hydrogen, has a conversion of 40%, while Rxn-2 has a conversion rate of 30%.

The two reforming reactions are endothermic, so heat must be supplied to the reactor to maintain the reactor temperature. Specify the temperature of the outlet stream, Combustor Feed, at 1700 °F, so that HYSYS will calculate the required duty.

Install the reactor and define it as indicated below.

Conversion Reactor [Reformer]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlets	Natural Gas
		Reformer Steam
	Vapour Outlet	Combustor Feed
	Liquid Outlet	Reformer Liq
	Energy	Reformer Q
Design [Parameters]	Optional Heat Transfer	Heating
Worksheet [Conditions]	Combustor Feed Temperature	1700 °F
Reactions [Details]	Reaction Set	Reformer Rxn Set
Comments	$\text{CH}_4 + \text{H}_2\text{O} \rightarrow \text{CO} + 3\text{H}_2$	
	$\text{CH}_4 + 2\text{H}_2\text{O} \rightarrow \text{CO}_2 + 4\text{H}_2$	

## Installing the Combustor

This reactor is adiabatic, so there is no energy stream and you do not have to specify the outlet temperature.

The Combustor is the second conversion reactor. The feed streams for the Combustor include the Reformer product, Air stream and Comb. Steam streams. The air stream is the source of the nitrogen for the required  $\text{H}_2:\text{N}_2$  ratio in the synthesis end product. The oxygen in the air is consumed in the combustion of methane. Any remaining methane in the Combustor is eliminated by this reaction.



HYSYS automatically ranks the three reactions in the Combustor Rxn Set. Since  $\text{H}_2\text{O}$  is a reactant in the combustion reaction (Rxn-1) and is a product in the two reforming reactions (Rxn-2 and Rxn-3), HYSYS provides a lower rank for the combustion reaction. An equal rank is given to the reforming reactions. With this ranking, the combustion reaction proceeds until its specified conversion is met or a limiting reactant is depleted. The reforming reactions then proceed based on the remaining methane.

Install the Combustor and define it as indicated below.

Reactions of equal ranking can have an overall specified conversion between 0% and 100%.

Conversion Reactor [Combustor]		
Tab [Page]	In this cell...	Enter...
<b>Design [Connections]</b>	Inlets	Combustor Feed
		Air
		Comb. Steam
	Vapour Outlet	Mid Combust
	Liquid Outlet	Mid Liq
<b>Reactions [Details]</b>	Reaction Set	Combustor Rxn Set
	Rxn-1 Conversion	35%
	Rxn-2 Conversion	65%
	Rxn-3 Conversion	100%
<b>Comments</b>	$\text{CH}_4 + \text{H}_2\text{O} \rightarrow \text{CO} + 3\text{H}_2$	
	$\text{CH}_4 + 2\text{H}_2\text{O} \rightarrow \text{CO}_2 + 4\text{H}_2$	
	$\text{CH}_4 + 2\text{O}_2 \rightarrow \text{CO}_2 + 2\text{H}_2\text{O}$	

## Shift Reactors

The three shift reactors are all equilibrium reactors within which the water-gas shift reaction occurs. In the Combustor Shift reactor, the equilibrium shift reaction takes place and would occur with the reactions in the Combustor. A separate reactor must be used in the model because equilibrium and conversion reactions cannot be combined within a reaction set.



Install the following three equilibrium reactors as shown below:

Equilibrium Reactor [Combustor Shift]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlets	Mid Combust
	Vapour Outlet	Shift1 Feed
	Liquid Outlet	Mid Com Liq
Reactions [Details]	Reaction Set	Shift Rxn Set
Comments	Reaction: $\text{CO} + \text{H}_2\text{O} \rightleftharpoons \text{CO}_2 + \text{H}_2$	

Equilibrium Reactor [Shift Reactor 1]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlets	Shift1 Feed
	Vapour Outlet	Shift2 Feed
	Liquid Outlet	Shift1 Liq
	Energy	Shift1 Q
Design [Parameters]	Optional Heat Transfer	Cooling
Worksheet [Conditions]	Shift2 Feed Temperature	850°F
Reactions [Details]	Reaction Set	Shift Rxn Set
Comments	Reaction: $\text{CO} + \text{H}_2\text{O} \rightleftharpoons \text{CO}_2 + \text{H}_2$	

Equilibrium Reactor [Shift Reactor 2]		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Feeds	Shift2 Feed
	Vapour Outlet	Synthesis Gas
	Liquid Outlet	Shift2 Liq
	Energy	Shift2 Q
Design [Parameters]	Optional Heat Transfer	Cooling
Worksheet [Conditions]	Synthesis Gas Temperature	750°F
Reactions [Details]	Reaction Set	Shift Rxn Set
Comments	Reaction: $\text{CO} + \text{H}_2\text{O} \rightleftharpoons \text{CO}_2 + \text{H}_2$	



## C2.3.2 Installing Adjust Operations

### Steam flow Rate

To control the temperature of the combustion reaction, the flow rate of steam to the Combustor is adjusted. Since the Combustor is modeled as two separate reactors, the temperature of the equilibrium reactor (Combustor Shift) is targeted. An ADJUST operation is used to manipulate the Comb. Steam flow rate to maintain the Combustor Shift temperature at 1700°F.

The same Adjust could be accomplished by selecting the temperature of the stream Shift1 Feed.

Adjust [ADJ-1]		
Tab	In this cell...	Enter...
Connections	Adjusted Object	Comb. Steam
	Adjusted Variable	Molar Flow
	Target Object	Combustor Shift
	Target Variable	Vessel Temp.
	Spec. Target Value	1700°F
Parameters	Method	Secant
	Tolerance	0.1°F
	Step Size	50 lbmole/hr
	Maximum Iterations	25

Click the **Start** button to begin the Adjust operation.

### Air Flow Rate

To control the H<sub>2</sub>:N<sub>2</sub> molar ratio in the Synthesis Gas stream, calculate the ratio in a Spreadsheet and then use an Adjust operation. The Synthesis Gas should have an H<sub>2</sub>:N<sub>2</sub> molar ratio slightly greater than 3:1. Prior to entering the ammonia plant, hydrogen is used to rid the synthesis gas of any remaining CO and CO<sub>2</sub>.

1. Create a Spreadsheet and change the Spreadsheet Name to **SSRatio**. Import the following variables:
  - Synthesis Gas, Comp. Molar Flow, Hydrogen
  - Synthesis Gas, Comp. Molar Flow, Nitrogen
2. Assign the Hydrogen value to cell B1, and the Nitrogen value to cell B2.



3. In cell B4, calculate the H<sub>2</sub>:N<sub>2</sub> ratio using the following formula:

$$+B1[\text{cell that contains flow of H}_2]/B2[\text{cell that contains flow of N}_2]$$

The Spreadsheet tab of the Spreadsheet view should appear similar to the following.

Figure C2.4

	A	B	C	D
1	Hydrogen	0.2049		
2	Nitrogen	0.0672		
3				
4	H2:N2 Ratio	3.050		
5				
6				
7				
8				

4. Click the **Parameters** tab and define the **Variable** name for the B4 cell as H<sub>2</sub>:N<sub>2</sub> Ratio.
5. Install the Adjust operation as shown below.

Adjust [ADJ-2]		
Tab	In this cell...	Enter...
Connections	Adjusted Variable	Air Molar Flow
	Target Variable	SSRatio, B4: H2:N2 Ratio
	Spec. Target Value	3.05
Parameters	Method	Secant
	Tolerance	0.005 lbmole/hr
	Step Size	39.68 lbmole/hr
	Maximum Iterations	20

6. Click the **Start** button to begin the Adjust operation.

The Secant method is used for both Adjust operations even though each adjusted variable will have an effect on the other operation's target variable. The close proximity of the logical operations in the flowsheet increases the possibility of cycling behaviour if the Simultaneous method is used. Therefore, it is advantageous to attempt to iterate on one Adjust and then solve the other.



# C2.4 Results

## Workbook Case [Main]

### Energy Streams Tab

Figure C2.5

Name	Reformer Q	Shift1 Q	Shift2 Q
Heat Flow [Btu/hr]	2.238e+007	7.349e+006	1.262e+006

### Material Streams Tab

Figure C2.6

Name	Natural Gas	Reformer Steam	Air	Comb. Steam	Combustor Feed	Reformer Liq	Mid Combust
Vapour Fraction	1.0000	1.0000	1.0000	1.0000	1.0000	0.0000	1.0000
Temperature [F]	700.0	475.0	60.00	475.0	1700	1700	1479
Pressure [psia]	500.0	500.0	500.0	500.0	500.0	500.0	500.0
Molar Flow [lbmole/hr]	200.0	520.0	107.2	55.22	1000	0.0000	1260
Mass Flow [lb/hr]	3209	9368	3092	994.8	1.258e+004	0.0000	1.666e+004
Liquid Volume Flow [barrel/day]	733.8	642.7	244.7	68.26	1975	0.0000	2502
Heat Flow [Btu/hr]	-5.115e+006	-5.254e+007	-2.574e+004	-5.580e+006	-3.528e+007	0.0000	-4.088e+007
Name	Mid Liq	Shift1 Feed	Mid Com Liq	Shift2 Feed	Shift1 Liq	Synthesis Gas	Shift2 Liq
Vapour Fraction	0.0000	1.0000	0.0000	1.0000	0.0000	1.0000	0.0000
Temperature [F]	1479	1440	1440	850.0	850.0	750.0	750.0
Pressure [psia]	500.0	500.0	500.0	500.0	500.0	500.0	500.0
Molar Flow [lbmole/hr]	0.0000	1260	0.0000	1260	0.0000	1260	0.0000
Mass Flow [lb/hr]	0.0000	1.666e+004	0.0000	1.666e+004	0.0000	1.666e+004	0.0000
Liquid Volume Flow [barrel/day]	0.0000	2447	0.0000	2590	0.0000	2620	0.0000
Heat Flow [Btu/hr]	0.0000	-4.088e+007	0.0000	-4.823e+007	0.0000	-4.951e+007	0.0000
Name	** New **						

Material Streams

Compositions

Energy Streams

Unit Ops



## Compositions Tab

Figure C2.7

Name	Natural Gas	Reformer Steam	Air	Comb. Steam	Combustor Feed	Reformer Liq	Mid Combust
Comp Mole Frac (Methane)	1.0000	0.0000	0.0000	0.0000	0.0600	0.0600	0.0000
Comp Mole Frac (H2O)	0.0000	1.0000	0.0000	1.0000	0.3200	0.3200	0.2518
Comp Mole Frac (CO)	0.0000	0.0000	0.0000	0.0000	0.0800	0.0800	0.0770
Comp Mole Frac (CO2)	0.0000	0.0000	0.0000	0.0000	0.0600	0.0600	0.0817
Comp Mole Frac (Hydrogen)	0.0000	0.0000	0.0000	0.0000	0.4800	0.4800	0.5222
Comp Mole Frac (Nitrogen)	0.0000	0.0000	0.7900	0.0000	0.0000	0.0000	0.0672
Comp Mole Frac (Oxygen)	0.0000	0.0000	0.2100	0.0000	0.0000	0.0000	0.0000
Name	Mid Liq	Shift1 Feed	Mid Com Liq	Shift2 Feed	Shift1 Liq	Synthesis Gas	Shift2 Liq
Comp Mole Frac (Methane)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Comp Mole Frac (H2O)	0.2518	0.2738	0.2737	0.2171	0.2172	0.2049	0.2051
Comp Mole Frac (CO)	0.0770	0.0990	0.0990	0.0423	0.0423	0.0301	0.0301
Comp Mole Frac (CO2)	0.0817	0.0598	0.0598	0.1164	0.1165	0.1286	0.1286
Comp Mole Frac (Hydrogen)	0.5222	0.5003	0.5003	0.5570	0.5568	0.5691	0.5689
Comp Mole Frac (Nitrogen)	0.0672	0.0672	0.0672	0.0672	0.0672	0.0672	0.0672
Comp Mole Frac (Oxygen)	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Name	** New **						
Material Streams   Compositions   Energy Streams   Unit Ops							







# X1 Case Linking

<b>X1.1 Process Description.....</b>	<b>3</b>
<b>X1.2 Building Flowsheet 1 .....</b>	<b>4</b>
X1.2.1 Setup .....	4
X1.2.2 Installing Streams .....	5
X1.2.3 Installing Unit Operations .....	5
<b>X1.3 Building Flowsheet 2 .....</b>	<b>8</b>
X1.3.1 Setup .....	8
X1.3.2 Installing Unit Operations .....	8
<b>X1.4 Creating a User Unit Operation.....</b>	<b>10</b>
X1.4.1 Initializing the User Unit Op.....	11
X1.4.2 Operation Execution .....	13








# X1.1 Process Description

This example uses the User Unit Operation to link two HYSYS cases together such that changes made to the first case (LinkCase1) are automatically and transparently propagated to the second (LinkCase2). This application demonstrates a method for copying the contents of a stream from one case to another automatically.

Figure X1.1



The User Unit Op is pre-configured with Visual Basic™ code. Inside the User Unit Op you will define two subroutines:

- **Initialize()** macro. The Initialize() macro sets the field names for the various stream feed and product connections and creates the following two text user variables:
  - **LinkCase** contains the path and file name of the target case to be linked. If the variable contains no value, the Initialize() code will set it to be the path to the currently open case and the file name **LinkCase2.hsc**.
  - **LinkStream** names a stream in the second case that will have the T, P, Flow and composition copied to it from the User Unit Op's feed stream. The target case and stream may optionally be changed explicitly from the Variables page of the User Unit Op.
- **Execute()** macro. The Execute() macro uses the GetObject method to open the target link case, which will initially be hidden. It then attempts to locate the material stream named by the LinkStream variable in the target case. If a stream is attached to the Feeds1 nozzle of the User Unit Op, the stream conditions and compositions are then copied between the streams.

All the stream names are in lower **case**.



The use of the `DuplicateFluid` method to copy the stream parameters requires identical property packages in both simulation cases. The example code instead uses a technique of explicitly copying T and P and then searches for components by name in order to copy their molar flow. Components that are not available in the target case are ignored.

Also, the definition of User Unit Op usually involves the definition of three macros:

- **Initialize()**
- **Execute()**
- **StatusQuery()** For this example, the `StatusQuery()` macro is commented-out to avoid the overhead of having that macro called. Removing the `StatusQuery()` code entirely would accomplish the same thing, but it is highly recommended that `StatusQuery()` be implemented to provide valuable user feedback. This implementation is left as an exercise for the user.

## X1.2 Building Flowsheet 1

### X1.2.1 Setup

1. Define a Peng Robinson Stryjek Vera (PRSV) property package.
2. Select the following components: C1, C2, C3, i-C4.
3. Set the unit preferences to SI.



## X1.2.2 Installing Streams

Specify streams **feed** and **cold\_liq2** as shown.

Stream Name	feed	cold_liq2
In this cell...	Enter...	Enter...
Temperature [C]	11	-98
Pressure [kPa]	5066	152
Molar Flow [kgmole/h]	100	7.5
Comp Mole Frac [C1]	0.5333	0.0388
Comp Mole Frac [C2]	0.2667	0.4667
Comp Mole Frac [C3]	0.1333	0.3883
Comp Mole Frac [i-C4]	0.0667	0.1062

## X1.2.3 Installing Unit Operations

Enter the Simulation Environment and add the following unit operations to the flowsheet.

### Add Separators

Separator Name	V-100	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	feed
	Vapour Outlet	feed_vap
	Liquid Outlet	feed_liq
Design [Parameters]	Delta P	0 kPa
V-101		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	precooled
	Vapour Outlet	cooled_vap
	Liquid Outlet	cooled_liq
Design [Parameters]	Delta P	0 kPa
V-102		
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	expanded
	Vapour Outlet	cold_vap
	Liquid Outlet	cold_liq
Design [Parameters]	Delta P	0 kPa



## Add a Heat Exchanger

Heat Exchanger Name	E-100	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Tube Side Inlet	feed_vap
	Tube Side Outlet	precooled
	Shell Side Inlet	cold_liq2
	Shell Side Outlet	rich gas
Design [Parameters]	Heat Exchanger Model	Exchanger Design (End Point)
	Heat Leak/Loss	none
	Tube Side Delta P	15 kPa
	Shell Side Delta P	15 kPa
	UA	4000 KJ/C-h
Rating [Sizing]	First Tube Pass Flow	Counter

## Add an Expander

Expander Name	K-100	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	cooled_vap
	Outlet	expanded
	Energy	shaft work
Design [Parameters]	Efficiency (Adiabatic)	75%
Worksheet [Conditions]	Pressure (stream: expanded)	152 kPa

## Add a Compressor

Compressor Name	K-101	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	cold_vap
	Outlet	compressed
	Energy	shaft work
Design [Parameters]	Efficiency (Adia)	75%



# Add a Recycle Operation

Recycle	RCY-1	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	cold_liq
	Outlet	cold_liq2

The case should converge immediately.

Save the case as **LinkCase1.hsc**.



# X1.3 Building Flowsheet 2

## X1.3.1 Setup

Now you will create the target case for the linked case.

1. Define the same property package as (PRSV) as Flowsheet 1.
2. Select SI units in the Session Preferences.
3. Select the following components: C1, C2, C3, i-C4, H2O.

## X1.3.2 Installing Unit Operations

Enter the Simulation Environment and enter the following unit operations.

### Add Compressors

Compressor Name	K-100	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	compressed
	Outlet	hot33atm
	Energy	q1
Design [Parameters]	Efficiency (Adia)	75%
Worksheet [Conditions]	Pressure (stream: hot33atm)	3344.725 kPa
	K-101	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	cool33atm
	Outlet	hot100atm
	Energy	q2
Design [Parameters]	Efficiency (Adia)	75%
Worksheet [Conditions]	Pressure (stream: hot100atm)	10150 kPa



## Add Heat Exchangers

Heat Exchanger Name	E-100	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Tube Side Inlet	hot33atm
	Tube Side Outlet	cool33atm
	Shell Side Inlet	wtr1
	Shell Side Outlet	wtr1b
Design [Parameters]	Heat Exchanger Model	Exchanger Design (End Point)
	Tube Side Delta P	15 kPa
	Shell Side Delta P	15 kPa
Rating [Sizing]	First Tube Pass Flow Direction	Counter
Worksheet [Conditions]	Temperature (stream: cool33atm)	17°C
	Temperature (stream: wtr1b)	25°C
	E-101	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Tube Side Inlet	hot100atm
	Tube Side Outlet	sales
	Shell Side Inlet	wtr2
	Shell Side Outlet	wtr2b
Design [Parameters]	Heat Exchanger Model	Exchanger Design (End Point)
	Tube Side Delta P	15 kPa
	Shell Side Delta P	15 kPa
Rating [Sizing]	First Tube Pass Flow Direction	Counter
Worksheet [Conditions]	Temperature (stream: sales)	20°C
	Temperature (stream: wtr2b)	25°C



# Add a Tee

Tee	T-100	
Tab [Page]	In this cell...	Enter...
Design [Connections]	Inlet	cooling water
	Outlet	wtr2, wtr1
Worksheet [Conditions]	Temperature (stream: cooling water)	11°C
	Pressure (stream: cooling water)	202.6 kPa
Worksheet [Composition]	H2O (stream: cooling water)	1.0000

- Once you have completed specifying this flowsheet, save the case as **LinkCase2.hsc** and close it.

## X1.4 Creating a User Unit Operation

Now that both cases have been created, you can create the link between them.

- Open **LinkCase1.hsc**.
- Add a User Unit Op to the flowsheet. When you add a Unit Op, HYSYS asks you for the type. Click the **Create Type** button, then type **Case Linking** in the input field and click the **OK** button.


Next you will define the User Unit Op. Defining the User Unit Op involves writing two different subroutines.

- Initialize.** Defines material and energy feed/product streams and creates user variables.
  - Execute.** Opens the target case, finds the target stream and copies the stream conditions from the main case.
- In the User Unit Op view **Design** tab, select the **Code** page.
  - Click the **Edit** button. The Edit Existing Code view appears.



## X1.4.1 Initializing the User Unit Op

The following table contains a listing of the code required to implement this operation, along with a brief description of what the code means. Partitions placed in the code are made only to clearly associate the relevant code with the explanation. Also, indentations made in the code are common with standard programming practices.

Code	Explanation
<b>Sub Initialize ()</b>	Signifies the Start of the initialization subroutine. You do not have to add it as it should already be there.
<pre> On Error GoTo Catch ' Preparing the interface ActiveObject.Feeds1Name = "Feed" ActiveObject.Products1Name = "Unused Prod1" ActiveObject.Feeds2Name = "Unused Feed2" ActiveObject.Products2Name = "Unused Prod2" </pre>	<p>If an error occurs during the execution of this subroutine, go to the line designated 'Catch'.</p> <p>You are setting the names that will be associated with the energy and material (primary and secondary) inlet and exit connections.</p> 
<pre> ActiveObject.Feeds2Active = False ActiveObject.Products2Active = False ActiveObject.EnergyFeedsActive = False ActiveObject.EnergyProductsActive = False </pre>	Deactivates the secondary inlet and exit connections as well as the energy inlet and exit connections. After the initialization subroutine has been successfully implemented, the checkboxes associated with the secondary material connections and energy connections should be deactivated as shown in the figure above.
<pre> ' Adding user variables Dim LinkCase As Object ' This UV will hold the Linked case name Set LinkCase = ActiveObject.CreateUserVariable("LinkCas e", "LinkCase", uvtText, utcNull,0) </pre>	Creates a text user variables called <b>LinkCase</b> . This will appear on the Variables page of the Design tab along with the current values. This variable holds the path and name of the linked case.
<pre> Dim LinkStream As Object ' This UV will hold the Linked stream name Set LinkStream = ActiveObject.CreateUserVariable("LinkStr eam", "LinkStream", uvtText, utcNull,0) </pre>	Creates a text user variables called <b>LinkStream</b> . This will appear on the Variables page of the Design tab along with the current values. This variable holds the name of the stream to link to.
<pre> LinkCase.Variable.Value = ActiveObject.SimulationCase.Path &amp; "LinkCase2.hsc" </pre>	This sets the linked case path to be the same as the current case and sets the name to 'LinkCase2.hsc'.



Code	Explanation
Dim myFeeds As Object Set myFeeds = ActiveObject.Feeds1	Declares the 'myFeeds' variable and sets it to the feed streams collection of the operation.
' Check if a stream name is already defined If Not LinkStream.Variable.IsKnown Then	Checks if a linked stream name is already defined.
If myFeeds.Count > 0 Then LinkStream.Variable.Value = myFeeds.Item(0).name	If a feed stream is connected to the unit operation, use that stream name as the linked stream name.
else LinkStream.Variable.Value = "feed" end if end if	If no stream is connected as feed, use the default listed stream name of 'feed'.
Exit Sub Catch: MsgBox "Initialize Error"	
<b>End Sub</b>	Signifies the end of the initialization subroutine. This line does not need to be added.

1. Once this code is entered, press the **OK** button to close the Edit Existing Code view.
2. On the **Code** page of the **Design** tab, click the **Initialize** button.
3. Select the **Connections** page of the **Design** tab. It should contain their new designations.
4. Select the **Variables** page. The LinkCase should contain the case LinkCase2, including the path. The LinkStream variable should contain 'feed'.
5. Select the **Connections** page. If the feed drop-down list is empty, the value of LinkStream variable (Variables page) should be 'feed'.



## X1.4.2 Operation Execution

Code	Explanation
<b>Sub Execute ( )</b>	Signifies the Start of the operation execution subroutine. You do not have to add this line as it should already be there.
On Error Goto EarlyGrave	If an error occurs during the execution of this subroutine, go to the line of code designated 'EarlyGrave'.
<pre>Dim Status As String  Dim LinkCase As Object Set LinkCase = ActiveObject.GetUserVariable("LinkCase")  Dim LinkStream As Object ' This UV will hold the Linked stream name Set LinkStream = ActiveObject.GetUserVariable("LinkStream ")</pre>	Connects the variables LinkCase and LinkStream to their corresponding user variables.
<pre>Dim myFeeds As Object Set myFeeds = ActiveObject.Feeds1 if myFeeds.Count &lt;&gt;1 Then Exit Sub end if</pre>	If the number of streams specified in the Feed list is not 1 then exit the subroutine.
<pre>Dim Case2 As Object Set Case2 = GetObject(LinkCase.Variable.Value)</pre>	Creates a reference to the LinkCase user variable called Case2.
<pre>Dim Case2FS As Object Set Case2FS = Case2.Flowsheet</pre>	Creates a reference to the flowsheet inside Case2 (LinkCase) called Case2FS.
<pre>Dim Case1FS As Object Set Case1FS = ActiveObject.Flowsheet</pre>	Creates a reference to the current flowsheet called Case1FS.
<pre>Dim Case2Strm As Object Set Case2Strm = Case2FS.MaterialStreams.Item(CStr(LinkStream.Variable.Value))</pre>	Creates a reference to a stream in the other case. The stream's name is the value of the user variable LinkStream.
<pre>Dim Case1Strm As Object Set Case1Strm = myFeeds.Item(0)</pre>	Creates a reference to stream currently in the primary feed list.
<pre>Case2Strm.TemperatureValue = Case1Strm.TemperatureValue Case2Strm.PressureValue = Case1Strm.PressureValue</pre>	Sets the Temperature and Pressure values of Case2Strm to those of Case1Strm.



Code	Explanation
<pre>Dim Case1CMFs As Variant Case1CMFs = Case1Strm.ComponentMolarFlowValue</pre>	Creates an array containing the molar flow of Case1Strm. Note that Set was not used so changes made to Case1CMFs will not affect Case1Strm.
<pre>Dim Case2CMFs As Variant Case2CMFs = Case2Strm.ComponentMolarFlowValue</pre>	Creates an array containing the molar flow of Case2Strm. Note that Set was not used so changes made to Case2CMFs will not affect Case2Strm.
<pre>On Error GoTo NoComp Dim Comp As Object i = 0 For Each Comp In Case2FS.FluidPackage.Components Case2CMFs(i) = 0.0 CompName = Comp.name n = Case1FS.FluidPackage.Components.index(CompName) Case2CMFs(i) = Case1CMFs(n) NoComp: i = i + 1 Next Comp</pre>	For every component i in the Case2FS, you set the molar flow of component i in the Case2CMFs array to the flow of the same component in Case1CMFs array.
<pre>On Error GoTo EarlyGrave</pre>	
<pre>Case2Strm.ComponentMolarFlowValue = Case2CMFs</pre>	This passes the value of Case2CMFs to the Case2Strm.
<pre>ActiveObject.SolveComplete</pre>	Signifies the Unit Operation has solved. It is used to minimize the number of times the User Unit Op's Execute() is called.
<pre>Exit Sub EarlyGrave: MsgBox "Execute Error"</pre>	
<pre><b>End Sub</b></pre>	Signifies the end of the initialization subroutine. This line does not need to be added.

When you are finished, activate the view by selecting the 'compressed' stream as the Feed on the Connections page of the Design tab. Ensure that the Link Stream stream name is also 'compressed'.

**The Unit Op will not appear 'solved' on the flowsheet, even though it is. This is because HYSYS expects it to have a fully defined product stream.**